# **X11 Input Extension Protocol Specification**

Version 1.0

X Consortium Standard X Version 11, Release 6.7

Mark PatrickArdent ComputerGeorge SachsHewlett-Packard

Copyright © 1989, 1990, 1991 by Hewlett-Packard Company and Ardent Computer

Permission to use, copy, modify, and distribute this documentation for any purpose and without fee is hereby granted, provided that the above copyright notice and this permission notice appear in all copies. Ardent and Hewlett-Packard make no representations about the suitability for any purpose of the information in this document. It is provided "as is" without express or implied warranty.

Copyright © 1989, 1990, 1991, 1992 X Consortium

Permission is hereby granted, free of charge, to any person obtaining a copy of this software and associated documentation files (the "Software"), to deal in the Software without restriction, including without limitation the rights to use, copy, modify, merge, publish, distribute, sublicense, and/or sell copies of the Software, and to permit persons to whom the Software is furnished to do so, subject to the following conditions:

The above copyright notice and this permission notice shall be included in all copies or substantial portions of the Software.

THE SOFTWARE IS PROVIDED "AS IS", WITHOUT WARRANTY OF ANY KIND, EXPRESS OR IMPLIED, INCLUDING BUT NOT LIMITED TO THE WARRANTIES OF MERCHANTABILITY, FITNESS FOR A PARTICULAR PURPOSE AND NONINFRINGE-MENT. IN NO EVENT SHALL THE X CONSORTIUM BE LIABLE FOR ANY CLAIM, DAMAGES OR OTHER LIABILITY, WHETHER IN AN ACTION OF CONTRACT, TORT OR OTHERWISE, ARISING FROM, OUT OF OR IN CONNECTION WITH THE SOFTWARE OR THE USE OR OTHER DEALINGS IN THE SOFTWARE.

Except as contained in this notice, the name of the X Consortium shall not be used in advertising or otherwise to promote the sale, use or other dealings in this Software without prior written authorization from the X Consortium.

X Window System is a trademark of The Open Group.

## **1.1. Input Extension Overview**

This document defines an extension to the X11 protocol to support input devices other than the core X keyboard and pointer. An accompanying document defines a corresponding extension to Xlib (similar extensions for languages other than C are anticipated). This first section gives an overview of the input extension. The next section defines the new protocol requests defined by the extension. We conclude with a description of the new input events generated by the additional input devices.

# 1.2. Design Approach

The design approach of the extension is to define requests and events analogous to the core requests and events. This allows extension input devices to be individually distinguishable from each other and from the core input devices. These requests and events make use of a device identifier and support the reporting of n-dimensional motion data as well as other data that is not reportable via the core input events.

# **1.3.** Core Input Devices

The X server core protocol supports two input devices: a pointer and a keyboard. The pointer device has two major functions. First, it may be used to generate motion information that client programs can detect. Second, it may also be used to indicate the current location and focus of the X keyboard. To accomplish this, the server echoes a cursor at the current position of the X pointer. Unless the X keyboard has been explicitly focused, this cursor also shows the current location and focus of the X keyboard.

The X keyboard is used to generate input that client programs can detect.

The X keyboard and X pointer are referred to in this document as the *core devices*, and the input events they generate (**KeyPress**, **KeyRelease**, **ButtonPress**, **ButtonRelease**, and **MotionNotify**) are known as the *core input events*. All other input devices are referred to as *extension input devices* and the input events they generate are referred to as *extension input events*.

Note

This input extension does not change the behavior or functionality of the core input devices, core events, or core protocol requests, with the exception of the core grab requests. These requests may affect the synchronization of events from extension devices. See the explanation in the section titled "Event Synchronization and Core Grabs".

Selection of the physical devices to be initially used by the server as the core devices is left implementation-dependent. Requests are defined that allow client programs to change which physical devices are used as the core devices.

## **1.4. Extension Input Devices**

The input extension controls access to input devices other than the X keyboard and X pointer. It allows client programs to select input from these devices independently from each other and independently from the core devices.

A client that wishes to access a specific device must first determine whether that device is connected to the X server. This is done through the **ListInputDevices** request, which will return a list of all devices that can be opened by the X server. A client can then open one or more of these devices using the **OpenDevice** request, specify what events they are interested in receiving, and receive and process input events from extension devices in the same way as events from the X keyboard and X pointer. Input events from these devices are of extension types (**DeviceKey-Press, DeviceKeyRelease, DeviceButtonPress, DeviceButtonRelease, DeviceMotionNotify**, etc.) and contain a device identifier so that events of the same type coming from different input devices can be distinguished. Any kind of input device may be used as an extension input device. Extension input devices may have 0 or more keys, 0 or more buttons, and may report 0 or more axes of motion. Motion may be reported as relative movements from a previous position or as an absolute position. All valuators reporting motion information for a given extension input device must report the same kind of motion information (absolute or relative).

This extension is designed to accommodate new types of input devices that may be added in the future. The protocol requests that refer to specific characteristics of input devices organize that information by **input classes**. Server implementors may add new classes of input devices without changing the protocol requests. Input classes are unique numbers registered with the X Consortium. Each extension input device may support multiple input classes.

All extension input devices are treated like the core X keyboard in determining their location and focus. The server does not track the location of these devices on an individual basis, and therefore does not echo a cursor to indicate their current location. Instead, their location is determined by the location of the core X pointer. Like the core X keyboard, some may be explicitly focused. If they are not explicitly focused, their focus is determined by the location of the core X pointer.

Input events reported by the server to a client are of fi xed size (32 bytes). In order to represent the change in state of an input device the extension may need to generate a sequence of input events. A client side library (such as Xlib) will typically take these raw input events and format them into a form more convenient to the client.

## 1.4.1. Event Classes

In the core protocol a client registers interest in receiving certain input events directed to a window by modifying that window's event-mask. Most of the bits in the event mask are already used to specify interest in core X events. The input extension specifi es a different mechanism by which a client can express interest in events generated by this extension.

When a client opens a extension input device via the **OpenDevice** request, an **XDevice** structure is returned. Macros are provided that extract 32-bit numbers called **event classes** from that structure, that a client can use to register interest in extension events via the **SelectExtensionEvent** request. The event class combines the desired event type and device id, and may be thought of as the equivalent of core event masks.

# 1.4.2. Input Classes

Some of the input extension requests divide input devices into classes based on their functionality. This is intended to allow new classes of input devices to be defined at a later time without changing the semantics of these requests. The following input device classes are currently defined:

**KEY** The device reports key events.

# BUTTON

The device reports button events.

## VALUATOR

The device reports valuator data in motion events.

## PROXIMITY

The device reports proximity events.

## FOCUS

The device can be focused and reports focus events.

## FEEDBACK

The device supports feedbacks.

#### OTHER

The **ChangeDeviceNotify**, **DeviceMappingNotify**, and **DeviceStateNotify** macros may be invoked passing the **XDevice** structure returned for this device.

#### X Input Extension Protocol Specification

Each extension input device may support multiple input classes. Additional classes may be added in the future. Requests that support multiple input classes, such as the **ListInputDevices** function that lists all available input devices, organize the data they return by input class. Client programs that use these requests should not access data unless it matches a class defined at the time those clients were compiled. In this way, new classes can be added without forcing existing clients that use these requests to be recompiled.

## 2. Requests

Extension input devices are accessed by client programs through the use of new protocol requests. This section summarizes the new requests defined by this extension. The syntax and type definitions used below follow the notation used for the X11 core protocol.

#### 2.1. Getting the Extension Version

The GetExtensionVersion request returns version information about the input extension.

**GetExtensionVersion** 

name: STRING

=>

present: BOOL protocol-major-version: CARD16 protocol-minor-version: CARD16

The protocol version numbers returned indicate the version of the input extension supported by the target X server. The version numbers can be compared to constants defined in the header file **XI.h**. Each version is a superset of the previous versions.

#### 2.2. Listing Available Devices

A client that wishes to access a specific device must first determine whether that device is connected to the X server. This is done through the **ListInputDevices** request, which will return a list of all devices that can be opened by the X server.

ListInputDevices

#### =>

input-devices: LISTofDEVICEINFO

where

DEVICEINFO:	[type: ATOM id: CARD8 num_classes: CARD8 use: {IsXKeyboard, IsXPointer, IsExtensionDevice} info: LISTofINPUTINFO name: STRING8]
INPUTINFO:	{KEYINFO, BUTTONINFO, VALUATORINFO}
KEYINFO:	[class: CARD8 length: CARD8 min-keycode: KEYCODE max-keycode: KEYCODE num-keys: CARD16]

BUTTONINFO:	[class: CARD8 length: CARD8 num-buttons: CARD16]
VALUATORINFO:	[class: CARD8 length: CARD8 num_axes: CARD8 mode: SETofDEVICEMODE motion_buffer_size: CARD32 axes: LISTofAXISINFO]
AXISINFO:	[resolution: CARD32 min-val: CARD32 max-val: CARD32]
DEVICEMODE:	{Absolute, Relative}
Errors: None	

This request returns a list of all devices that can be opened by the X server, including the core X keyboard and X pointer. Some implementations may open all input devices as part of X initialization, while others may not open an input device until requested to do so by a client program.

• The information returned for each device is as follows:

The **type** field is of type **Atom** and indicates the nature of the device. Clients may determine device types by invoking the **XInternAtom** request passing one of the names defined in the header file **XI.h**. The following names have been defined to date:

MOUSE TABLET **KEYBOARD TOUCHSCREEN** TOUCHPAD **BUTTONBOX** BARCODE KNOB\_BOX TRACKBALL **QUADRATURE SPACEBALL** DATAGLOVE EYETRACKER **CURSORKEYS** FOOTMOUSE **ID MODULE ONE\_KNOB** NINE\_KNOB

The **id** is a small cardinal value in the range 0-128 that uniquely identifies the device. It is assigned to the device when it is initialized by the server. Some implementations may not open an input device until requested by a client program, and may close the device when the last client accessing it requests that it be closed. If a device is opened by a client program via **XOpenDevice**, then closed via **XCloseDevice**, then opened again, it is not guaranteed to have the same id after the second open request.

The **num\_classes** fi eld is a small cardinal value in the range 0-255 that specifi es the number of input classes supported by the device for which information is returned by **ListIn-putDevices**. Some input classes, such as class **Focus** and class **Proximity** do not have any information to be returned by **ListInputDevices**.

The **use** field specifies how the device is currently being used. If the value is **IsXKey-board**, the device is currently being used as the X keyboard. If the value is **IsXPointer**, the device is currently being used as the X pointer. If the value is **IsXExtensionDevice**, the device is available for use as an extension device.

The **name** fi eld contains a pointer to a null-terminated string that corresponds to one of the defi ned device types.

• InputInfo is one of: KeyInfo, ButtonInfo or ValuatorInfo. The first two fields are common to all three:

The **class** fi eld is a cardinal value in the range 0-255. It uniquely identifies the class of input for which information is returned.

The **length** fi eld is a cardinal value in the range 0-255. It specifi es the number of bytes of data that are contained in this input class. The length includes the class and length fi elds.

The remaining information returned for input class **KEYCLASS** is as follows:

**min\_keycode** is of type KEYCODE. It specifies the minimum keycode that the device will report. The minimum keycode will not be smaller than 8.

**max\_keycode** is of type KEYCODE. It specifies the maximum keycode that the device will report. The maximum keycode will not be larger than 255.

num\_keys is a cardinal value that specifi es the number of keys that the device has.

The remaining information returned for input class **BUTTONCLASS** is as follows:

num\_buttons is a cardinal value that specifi es the number of buttons that the device has.

The remaining information returned for input class **VALUATORCLASS** is as follows:

**mode** is a constant that has one of the following values: **Absolute** or **Relative**. Some devices allow the mode to be changed dynamically via the **SetDeviceMode** request.

**motion\_buffer\_size** is a cardinal number that specifi es the number of elements that can be contained in the motion history buffer for the device.

The **axes** fi eld contains a pointer to an AXISINFO struture.

• The information returned for each axis reported by the device is:

The **resolution** is a cardinal value in counts/meter.

The **min\_val** fi eld is a cardinal value in that contains the minimum value the device reports for this axis. For devices whose mode is **Relative**, the min\_val fi eld will contain 0.

The **max\_val** fi eld is a cardinal value in that contains the maximum value the device reports for this axis. For devices whose mode is **Relative**, the max\_val fi eld will contain 0.

## 2.3. Enabling Devices

Client programs that wish to access an extension device must request that the server open that device. This is done via the **OpenDevice** request.

```
OpenDevice
id: CARD8
=>
```

DEVICE:	[device_id: XID num_classes: INT32 classes: LISTofINPUTCLASSINFO]
INPUTCLASSINFO:	[input_class: CARD8 event_type_base: CARD8]

Errors: Device

This request returns the event classes to be used by the client to indicate which events the client program wishes to receive. Each input class may report several event classes. For example, input class **Keys** reports **DeviceKeyPress** and **DeviceKeyRelease** event classes. Input classes are unique numbers registered with the X Consortium. Input class **Other** exists to report event classes that are not specific to any one input class, such as **DeviceMappingNotify**, **ChangeDeviceNotify**, and **DeviceStateNotify**.

• The information returned for each device is as follows:

The **device\_id** is a number that uniquely identifies the device.

The num\_classes fi eld contains the number of input classes supported by this device.

• For each class of input supported by the device, the **InputClassInfo** structure contains the following information:

The input\_class is a small cardinal number that identifies the class of input.

The **event\_type\_base** is a small cardinal number that specifi es the event type of one of the events reported by this input class. This information is not directly used by client programs. Instead, the **Device** is used by macros that return extension event types and event classes. This is described in the section of this document entitled "Selecting Extension Device Events".

Before it exits, the client program should explicitly request that the server close the device. This is done via the **CloseDevice** request.

A client may open the same extension device more than once. Requests after the fi rst successful one return an additional **XDevice** structure with the same information as the fi rst, but otherwise have no effect. A single **CloseDevice** request will terminate that client's access to the device.

Closing a device releases any active or passive grabs the requesting client has established. If the device is frozen only by an active grab of the requesting client, the queued events are released when the client terminates.

If a client program terminates without closing a device, the server will automatically close that device on behalf of the client. This does not affect any other clients that may be accessing that device.

CloseDevice device: DEVICE

Errors: Device

# 2.4. Changing The Mode Of A Device

Some devices are capable of reporting either relative or absolute motion data. To change the mode of a device from relative to absolute, use the **SetDeviceMode** request. The valid values are **Absolute** or **Relative**.

This request will fail and return **DeviceBusy** if another client already has the device open with a different mode. It will fail and return **AlreadyGrabbed** if another client has the device grabbed. The request will fail with a **BadMatch** error if the requested mode is not supported by the device.

SetDeviceMode device: DEVICE mode: {Absolute, Relative}

Errors: Device, Match, Mode

=>

status: {Success, DeviceBusy, AlreadyGrabbed}

# 2.5. Initializing Valuators on an Input Device

Some devices that report absolute positional data can be initialized to a starting value. Devices that are capable of reporting relative motion or absolute positional data may require that their valuators be initialized to a starting value after the mode of the device is changed to **Absolute**. To initialize the valuators on such a device, use the **SetDeviceValuators** request.

SetDeviceValuators device: DEVICE fi rst\_valuator: CARD8 num\_valuators: CARD8 valuators: LISTOFINT32

Errors: Length, Device, Match, Value

=>

status: {Success, AlreadyGrabbed}

This request initializes the specifi ed valuators on the specifi ed extension input device. Valuators are numbered beginning with zero. Only the valuators in the range specifi ed by fi rst\_valuator and num\_valuators are set. If the number of valuators supported by the device is less than the expression fi rst\_valuator + num\_valuators, a **Value** error will result.

If the request succeeds, **Success** is returned. If the specifed device is grabbed by some other client, the request will fail and a status of **AlreadyGrabbed** will be returned.

# 2.6. Getting Input Device Controls

GetDeviceControl device: DEVICE control: XID Errors: Length, Device, Match, Value

=>

controlState: {DeviceState}

where

DeviceState: DeviceResolutionState

Errors: Length, Device, Match, Value

This request returns the current state of the specified device control. The device control must be supported by the target server and device or an error will result.

If the request is successful, a pointer to a generic DeviceState structure will be returned. The information returned varies according to the specified control and is mapped by a structure appropriate for that control.

GetDeviceControl will fail with a BadValue error if the server does not support the specified control. It will fail with a BadMatch error if the device does not support the specified control.

Supported device controls and the information returned for them include:

DEVICE_RESOLUTION:	[control: CARD16
	length: CARD16
	num_valuators: CARD8
	resolutions: LISTofCARD32
	min_resolutions: LISTofCARD32
	max_resolutions: LISTofCARD32]

This device control returns a list of valuators and the range of valid resolutions allowed for each. Valuators are numbered beginning with 0. Resolutions for all valuators on the device are returned. For each valuator i on the device, resolutions[i] returns the current setting of the resolution, min\_resolutions[i] returns the minimum valid setting, and max\_resolutions[i] returns the maximum valid setting.

When this control is specified, XGetDeviceControl will fail with a BadMatch error if the specified device has no valuators.

ChangeDeviceControl device: DEVICE XID: controlId control: DeviceControl

where

DeviceControl: DeviceResolutionControl

Errors: Length, Device, Match, Value

=>

status: {Success, DeviceBusy, AlreadyGrabbed}

ChangeDeviceControl changes the specifed device control according to the values specified in the DeviceControl structure. The device control must be supported by the target server and device or an error will result.

The information passed with this request varies according to the specified control and is mapped by a structure appropriate for that control.

ChangeDeviceControl will fail with a BadValue error if the server does not support the specified control. It will fail with a BadMatch error if the server supports the specified control, but the requested device does not. The request will fail and return a status of DeviceBusy if another client already has the device open with a device control state that conflicts with the one specified in the request. It will fail with a status of AlreadyGrabbed if some other client has grabbed the specified device. If the request succeeds, Success is returned. If it fails, the device control is left unchanged.

Supported device controls and the information specified for them include:

DEVICE_RESOLUTION:	[control: CARD16
	length: CARD16
	fi rst_valuator: CARD8
	num_valuators: CARD8
	resolutions: LISTofCARD32]

This device control changes the resolution of the specifi ed valuators on the specifi ed extension input device. Valuators are numbered beginning with zero. Only the valuators in the range specifi ed by fi rst\_valuator and num\_valuators are set. A value of -1 in the resolutions list indicates that the resolution for this valuator is not to be changed. num\_valuators specifi es the number of valuators in the resolutions list.

When this control is specified, XChangeDeviceControl will fail with a BadMatch error if the specified device has no valuators. If a resolution is specified that is not within the range of valid values (as returned by XGetDeviceControl) the request will fail with a BadValue error. If the number of valuators supported by the device is less than the expression first\_valuator + num\_valuators, a BadValue error will result.

If the request fails for any reason, none of the valuator resolutions will be changed.

#### 2.7. Selecting Extension Device Events

Extension input events are selected using the **SelectExtensionEvent** request.

SelectExtensionEvent window: WINDOW interest: LISTofEVENTCLASS

Errors: Window, Class, Access

This request specifies to the server the events within the specified window which are of interest to the client. As with the core **XSelectInput** function, multiple clients can select input on the same window.

**XSelectExtensionEvent** requires a list of *event classes*. An event class is a 32-bit number that combines an event type and device id, and is used to indicate which event a client wishes to receive and from which device it wishes to receive it. Macros are provided to obtain event classes from the data returned by the **XOpenDevice** request. The names of these macros correspond to the desired events, i.e. the **DeviceKeyPress** is used to obtain the event class for **DeviceKeyPress** events. The syntax of the macro invocation is:

DeviceKeyPress (device, event\_type, event\_class); device: DEVICE event\_type: INT event\_class: INT

The value returned in **event\_type** is the value that will be contained in the event type field of the **XDeviceKeyPressEvent** when it is received by the client. The value returned in **event\_class** is the value that should be passed in making an **XSelectExtensionEvent** request to receive **DeviceKeyPress** events.

For **DeviceButtonPress** events, the client may specify whether or not an implicit passive grab should be done when the button is pressed. If the client wants to guarantee that it will receive a **DeviceButtonRelease** event for each **DeviceButtonPress** event it receives, it should specify the **DeviceButtonPressGrab** event class as well as the **DeviceButtonPress** event class. This restricts the client in that only one client at a time may request **DeviceButtonPress** events from the same device and window if any client specifi es this class.

If any client has specified the **DeviceButtonPressGrab** class, any requests by any other client that specify the same device and window and specify **DeviceButtonPress** or **DeviceButtonPress-Grab** will cause an **Access** error to be generated.

If only the **DeviceButtonPress** class is specified, no implicit passive grab will be done when a button is pressed on the device. Multiple clients may use this class to specify the same device and window combination.

A client may also specify the **DeviceOwnerGrabButton** class. If it has specified both the **DeviceButtonPressGrab** and the **DeviceOwnerGrabButton** classes, implicit passive grabs will activate with owner\_events set to **True**. If only the **DeviceButtonPressGrab** class is specified, implicit passive grabs will activate with owner\_events set to **False**.

The client may select **DeviceMotion** events only when a button is down. It does this by specifying the event classes **Button1Motion** through **Button5Motion**, or **ButtonMotion**. An input device will only support as many button motion classes as it has buttons.

# 2.8. Determining Selected Events

To determine which extension events are currently selected from a given window, use **GetSelect-edExtensionEvents**.

GetSelectedExtensionEvents window: WINDOW

=>

this-client: LISTofEVENTCLASS all-clients: LISTofEVENTCLASS

Errors: Window

This request returns two lists specifying the events selected on the specifi ed window. One list gives the extension events selected by this client from the specifi ed window. The other list gives the extension events selected by all clients from the specifi ed window. This information is equivalent to that returned by your-event-mask and all-event-masks in a **GetWindowAttributes** request.

# 2.9. Controlling Event Propagation

Extension events propagate up the window hierarchy in the same manner as core events. If a window is not interested in an extension event, it usually propagates to the closest ancestor that is interested, unless the dont\_propagate list prohibits it. Grabs of extension devices may alter the set of windows that receive a particular extension event.

Client programs may control extension event propagation through the use of the following two requests.

**XChangeDeviceDontPropagateList** adds an event to or deletes an event from the do\_not\_propagate list of extension events for the specifi ed window. This list is maintained for the life of the window, and is not altered if the client terminates.

ChangeDeviceDontPropagateList window: WINDOW eventclass: LISTofEVENTCLASS mode: {AddToList, DeleteFromList}

Errors: Window, Class, Mode

This function modifies the list specifying the events that are not propagated to the ancestors of the specified window. You may use the modes **AddToList** or **DeleteFromList**.

GetDeviceDontPropagateList window: WINDOW

Errors: Window

=>

dont-propagate-list: LISTofEVENTCLASS

This function returns a list specifying the events that are not propagated to the ancestors of the specifi ed window.

## 2.10. Sending Extension Events

One client program may send an event to another via the **XSendExtensionEvent** function.

The event in the **XEvent** structure must be one of the events defined by the input extension, so that the X server can correctly byte swap the contents as necessary. The contents of the event are otherwise unaltered and unchecked by the X server except to force send\_event to **True** in the forwarded event and to set the sequence number in the event correctly.

XSendExtensionEvent returns zero if the conversion-to-wire protocol failed, otherwise it returns nonzero.

SendExtensionEvent

device: DEVICE destination: WINDOW propagate: BOOL eventclass: LISTofEVENTCLASS event: XEVENT

Errors: Device, Value, Class, Window

## 2.11. Getting Motion History

GetDeviceMotionEvents device: DEVICE start, stop: TIMESTAMP or CurrentTime

=>

nevents\_return: CARD32 mode\_return: {Absolute, Relative} axis\_count\_return: CARD8 events: LISTofDEVICETIMECOORD

where

DEVICETIMECOORD: [data:LISTofINT32 time:TIMESTAMP]

Errors: Device, Match

This request returns all positions in the device's motion history buffer that fall between the specifi ed start and stop times inclusive. If the start time is in the future, or is later than the stop time, no positions are returned.

The data fi eld of the DEVICETIMECOORD structure is a sequence of data items. Each item is of type INT32, and there is one data item per axis of motion reported by the device. The number of axes reported by the device is returned in the axis\_count variable.

The value of the data items depends on the mode of the device, which is returned in the mode variable. If the mode is Absolute, the data items are the raw values generated by the device. These may be scaled by the client program using the maximum values that the device can generate for each axis of motion that it reports. The maximum and minimum values for each axis are reported by the **ListInputDevices** request.

If the mode is Relative, the data items are the relative values generated by the device. The client program must choose an initial position for the device and maintain a current position by accumulating these relative values.

## 2.12. Changing The Core Devices

These requests are provided to change which physical device is used as the X pointer or X keyboard.

Note

Using these requests may change the characteristics of the core devices. The new pointer device may have a different number of buttons than the old one did, or the new keyboard device may have a different number of keys or report a different range of keycodes. Client programs may be running that depend on those characteristics. For example, a client program could allocate an array based on the number of buttons on the pointer device, and then use the button numbers received in button events as indicies into that array. Changing the core devices could cause such client programs to behave improperly or abnormally terminate.

These requests change the X keyboard or X pointer device and generate an **ChangeDeviceNotify** event and a **MappingNotify** event. The **ChangeDeviceNotify** event is sent only to those clients that have expressed an interest in receiving that event via the **XSelectExtensionEvent** request. The specified device becomes the new X keyboard or X pointer device. The location of the core device does not change as a result of this request.

These requests fail and return **AlreadyGrabbed** if either the specified device or the core device it would replace are grabbed by some other client. They fail and return **GrabFrozen** if either device is frozen by the active grab of another client.

These requests fail with a **BadDevice** error if the specified device is invalid, or has not previously been opened via **OpenDevice**.

#### **X Input Extension Protocol Specification**

To change the X keyboard device, use the **ChangeKeyboardDevice** request. The specified device must support input class Keys (as reported in the ListInputDevices request) or the request will fail with a **BadMatch** error. Once the device has successfully replaced one of the core devices, it is treated as a core device until it is in turn replaced by another ChangeDevice request, or until the server terminates. The termination of the client that changed the device will not cause it to change back. Attempts to use the CloseDevice request to close the new core device will fail with a BadDevice error.

The focus state of the new keyboard is the same as the focus state of the old X keyboard. If the new keyboard was not initialized with a **FocusRec**, one is added by the **ChangeKeyboardDevice** request. The X keyboard is assumed to have a **KbdFeedbackClassRec**. If the device was initialized without a **KbdFeedbackClassRec**, one will be added by this request. The **KbdFeedbackClassRec**. ClassRec will specify a null routine as the control procedure and the bell procedure.

ChangeKeyboardDevice device: DEVICE

Errors: Device, Match

=>

status: Success, AlreadyGrabbed, Frozen

To change the X pointer device, use the **ChangePointerDevice** request. The specifi ed device must support input class Valuators (as reported in the ListInputDevices request) or the request will fail with a BadMatch error. The valuators to be used as the x- and y-axes of the pointer device must be specified. Data from other valuators on the device will be ignored.

The X pointer device does not contain a **FocusRec**. If the new pointer was initialized with a **FocusRec**, it is freed by the **ChangePointerDevice** request. The X pointer is assumed to have a **ButtonClassRec** and a **PtrFeedbackClassRec**. If the device was initialized without a **ButtonClassRec** or a **PtrFeedbackClassRec**, one will be added by this request. The **ButtonClassRec** added will have no buttons, and the **PtrFeedbackClass-Rec** will specify a null routine as the control procedure.

If the specified device reports absolute positional information, and the server implementation does not allow such a device to be used as the X pointer, the request will fail with a **BadDevice** error.

Once the device has successfully replaced one of the core devices, it is treated as a core device until it is in turn replaced by another ChangeDevice request, or until the server terminates. The termination of the client that changed the device will not cause it to change back. Attempts to use the CloseDevice request to close the new core device will fail with a BadDevice error.

ChangePointerDevice device: DEVICE xaxis: CARD8 yaxis: CARD8

Errors: Device, Match

=>

status: Success, AlreadyGrabbed, Frozen

# 2.13. Event Synchronization And Core Grabs

Implementation of the input extension requires an extension of the meaning of event synchronization for the core grab requests. This is necessary in order to allow window managers to freeze all input devices with a single request.

The core grab requests require a **pointer\_mode** and **keyboard\_mode** argument. The meaning of these modes is changed by the input extension. For the **XGrabPointer** and **XGrabButton** requests, **pointer\_mode** controls synchronization of the pointer device, and **keyboard\_mode** controls the synchronization of all other input devices. For the **XGrabKeyboard** and **XGrabKey** requests, **pointer\_mode** controls the synchronization of all input devices except the X keyboard, while **keyboard\_mode** controls the synchronization of the keyboard. When using one of the core grab requests, the synchronization of extension devices is controlled by the mode specifi ed for the device not being grabbed.

# 2.14. Extension Active Grabs

Active grabs of extension devices are supported via the **GrabDevice** request in the same way that core devices are grabbed using the core GrabKeyboard request, except that a *Device* is passed as a function parameter. A list of events that the client wishes to receive is also passed. The **UngrabDevice** request allows a previous active grab for an extension device to be released.

To grab an extension device, use the **GrabDevice** request. The device must have previously been opened using the **OpenDevice** request.

GrabDevice device: DEVICE grab-window: WINDOW owner-events: BOOL event-list: LISTofEVENTCLASS this-device-mode: {Synchronous, Asynchronous} other-device-mode: {Synchronous, Asynchronous} time:TIMESTAMP or CurrentTime

=>

status: Success, AlreadyGrabbed, Frozen, InvalidTime, NotViewable

Errors: Device, Window, Value

This request actively grabs control of the specified input device. Further input events from this device are reported only to the grabbing client. This request overrides any previous active grab by this client for this device.

The event-list parameter is a pointer to a list of event classes. These are used to indicate which events the client wishes to receive while the device is grabbed. Only event classes obtained from the grabbed device are valid.

If owner-events is **False**, input events generated from this device are reported with respect to grab-window, and are only reported if selected by being included in the event-list. If owner-events is **True**, then if a generated event would normally be reported to this client, it is reported normally, otherwise the event is reported with respect to the grab-window, and is only reported if selected by being included in the event-list. For either value of owner-events, unreported events are discarded.

If this-device-mode is **Asynchronous**, device event processing continues normally. If the device is currently frozen by this client, then processing of device events is resumed. If this-device-mode is **Synchronous**, the state of the grabbed device (as seen by means of the protocol) appears to freeze, and no further device events are generated by the server until the grabbing client issues

a releasing **AllowDeviceEvents** request or until the device grab is released. Actual device input events are not lost while the device is frozen; they are simply queued for later processing.

If other-device-mode is **Asynchronous**, event processing is unaffected by activation of the grab. If other-device-mode is **Synchronous**, the state of all input devices except the grabbed one (as seen by means of the protocol) appears to freeze, and no further events are generated by the server until the grabbing client issues a releasing **AllowDeviceEvents** request or until the device grab is released. Actual events are not lost while the devices are frozen; they are simply queued for later processing.

This request generates **DeviceFocusIn** and **DeviceFocusOut** events.

This request fails and returns:

- AlreadyGrabbed If the device is actively grabbed by some other client.
- NotViewable If grab-window is not viewable.
- **InvalidTime** If the specified time is earlier than the last-grab-time for the specified device or later than the current X server time. Otherwise, the last-grab-time for the specified device is set to the specified time and **CurrentTime** is replaced by the current X server time.
- Frozen If the device is frozen by an active grab of another client.

If a grabbed device is closed by a client while an active grab by that client is in effect, that active grab will be released. Any passive grabs established by that client will be released. If the device is frozen only by an active grab of the requesting client, it is thawed.

To release a grab of an extension device, use UngrabDevice.

UngrabDevice device: DEVICE time: TIMESTAMP or CurrentTime

Errors: Device

This request releases the device if this client has it actively grabbed (from either **GrabDevice** or **GrabDeviceKey**) and releases any queued events. If any devices were frozen by the grab, **UngrabDevice** thaws them. The request has no effect if the specified time is earlier than the last-device-grab time or is later than the current server time.

This request generates **DeviceFocusIn** and **DeviceFocusOut** events.

An **UngrabDevice** is performed automatically if the event window for an active device grab becomes not viewable.

# 2.15. Passively Grabbing A Key

Passive grabs of buttons and keys on extension devices are supported via the **GrabDeviceButton** and **GrabDeviceKey** requests. These passive grabs are released via the **UngrabDeviceKey** and **UngrabDeviceButton** requests.

To passively grab a single key on an extension device, use **GrabDeviceKey**. That device must have previously been opened using the **OpenDevice** request.

GrabDeviceKey

device: DEVICE keycode: KEYCODE or AnyKey modifi ers: SETofKEYMASK or AnyModifi er modifi er-device: DEVICE or NULL grab-window: WINDOW owner-events: BOOL event-list: LISTofEVENTCLASS this-device-mode: {Synchronous, Asynchronous} other-device-mode: {Synchronous, Asynchronous}

Errors: Device, Match, Access, Window, Value

This request is analogous to the core **GrabKey** request. It establishes a passive grab on a device. Consequently, In the future:

- IF the device is not grabbed and the specifi ed key, which itself can be a modifi er key, is logically pressed when the specifi ed modifi er keys logically are down on the specifi ed modifi er device (and no other keys are down),
- AND no other modifi er keys logically are down,
- AND EITHER the grab window is an ancestor of (or is) the focus window OR the grab window is a descendent of the focus window and contains the pointer,
- AND a passive grab on the same device and key combination does not exist on any ancestor of the grab window,
- THEN the device is actively grabbed, as for **GrabDevice**, the last-device-grab time is set to the time at which the key was pressed (as transmitted in the **DeviceKeyPress** event), and the **DeviceKeyPress** event is reported.

The interpretation of the remaining arguments is as for **GrabDevice**. The active grab is terminated automatically when logical state of the device has the specified key released (independent of the logical state of the modifier keys).

Note that the logical state of a device (as seen by means of the X protocol) may lag the physical state if device event processing is frozen.

A modifi er of **AnyModifier** is equivalent to issuing the request for all possible modifi er combinations (including the combination of no modifi ers). It is not required that all modifi ers specifi ed have currently assigned keycodes. A key of **AnyKey** is equivalent to issuing the request for all possible keycodes. Otherwise, the key must be in the range specifi ed by min-keycode and maxkeycode in the **ListInputDevices** request. If it is not within that range, **GrabDeviceKey** generates a **Value** error.

**NULL** may be passed for the modifi er\_device. If the modifi er\_device is **NULL**, the core X keyboard is used as the modifi er\_device.

An Access error is generated if some other client has issued a GrabDeviceKey with the same device and key combination on the same window. When using AnyModifier or AnyKey, the request fails completely and the X server generates a Access error and no grabs are established if there is a conflicting grab for any combination.

This request cannot be used to grab a key on the X keyboard device. The core **GrabKey** request should be used for that purpose.

To release a passive grab of a single key on an extension device, use UngrabDeviceKey.

UngrabDeviceKey

device: DEVICE keycode: KEYCODE or AnyKey modifi ers: SETofKEYMASK or AnyModifi er modifi er-device: DEVICE or NULL grab-window: WINDOW

Errors: Device, Match, Window, Value, Alloc

## X Input Extension Protocol Specification

This request is analogous to the core **UngrabKey** request. It releases the key combination on the specified window if it was grabbed by this client. A modifier of **AnyModifier** is equivalent to issuing the request for all possible modifier combinations (including the combination of no modifiers). A key of **AnyKey** is equivalent to issuing the request for all possible keycodes. This request has no effect on an active grab.

**NULL** may be passed for the modifi er\_device. If the modifi er\_device is **NULL**, the core X keyboard is used as the modifi er\_device.

## 2.16. Passively Grabbing A Button

To establish a passive grab for a single button on an extension device, use GrabDeviceButton.

GrabDeviceButton

device: DEVICE button: BUTTON or AnyButton modifi ers: SETofKEYMASK or AnyModifi er modifi er-device: DEVICE or NULL grab-window: WINDOW owner-events: BOOL event-list: LISTofEVENTCLASS this-device-mode: {Synchronous, Asynchronous} other-device-mode: {Synchronous, Asynchronous}

Errors: Device, Match, Window, Access, Value

This request is analogous to the core **GrabButton** request. It establishes an explicit passive grab for a button on an extension input device. Since the server does not track extension devices, no cursor is specified with this request. For the same reason, there is no confine-to parameter. The device must have previously been opened using the **OpenDevice** request.

The **GrabDeviceButton** request establishes a passive grab on a device. Consequently, in the future,

- IF the device is not grabbed and the specifi ed button is logically pressed when the specifi ed modifi er keys logically are down (and no other buttons or modifi er keys are down),
- AND the grab window contains the device,
- AND a passive grab on the same device and button/ key combination does not exist on any ancestor of the grab window,
- THEN the device is actively grabbed, as for **GrabDevice**, the last-grab time is set to the time at which the button was pressed (as transmitted in the **DeviceButtonPress** event), and the **DeviceButtonPress** event is reported.

The interpretation of the remaining arguments is as for **GrabDevice**. The active grab is terminated automatically when logical state of the device has all buttons released (independent of the logical state of the modifi er keys).

Note that the logical state of a device (as seen by means of the X protocol) may lag the physical state if device event processing is frozen.

A modifi er of **AnyModifi er** is equivalent to issuing the request for all possible modifi er combinations (including the combination of no modifi ers). It is not required that all modifi ers specifi ed have currently assigned keycodes. A button of **AnyButton** is equivalent to issuing the request for all possible buttons. It is not required that the specifi ed button be assigned to a physical button.

**NULL** may be passed for the modifi er\_device. If the modifi er\_device is **NULL**, the core X keyboard is used as the modifi er\_device.

#### X Input Extension Protocol Specification

An Access error is generated if some other client has issued a GrabDeviceButton with the same device and button combination on the same window. When using AnyModifi er or AnyButton, the request fails completely and the X server generates a Access error and no grabs are established if there is a conflicting grab for any combination. The request has no effect on an active grab.

This request cannot be used to grab a button on the X pointer device. The core **GrabButton** request should be used for that purpose.

To release a passive grab of a button on an extension device, use UngrabDeviceButton.

#### UngrabDeviceButton

device: DEVICE button: BUTTON or AnyButton modifi ers: SETofKEYMASK or AnyModifi er modifi er-device: DEVICE or NULL grab-window: WINDOW

Errors: Device, Match, Window, Value, Alloc

This request is analogous to the core UngrabButton request. It releases the passive button/key combination on the specifi ed window if it was grabbed by the client. A modifi ers of **AnyModifi er** is equivalent to issuing the request for all possible modifi er combinations (including the combination of no modifi ers). A button of **AnyButton** is equivalent to issuing the request for all possible buttons. This request has no effect on an active grab. The device must have previously been opened using the **OpenDevice** request otherwise a **Device** error will be generated.

**NULL** may be passed for the modifi er\_device. If the modifi er\_device is **NULL**, the core X keyboard is used as the modifi er\_device.

This request cannot be used to ungrab a button on the X pointer device. The core **UngrabButton** request should be used for that purpose.

#### 2.17. Thawing A Device

To allow further events to be processed when a device has been frozen, use AllowDeviceEvents.

AllowDeviceEvents

device: DEVICE event-mode: {AsyncThisDevice, SyncThisDevice, AsyncOtherDevices, ReplayThisdevice, AsyncAll, or SyncAll} time:TIMESTAMP or CurrentTime

Errors: Device, Value

The **AllowDeviceEvents** request releases some queued events if the client has caused a device to freeze. The request has no effect if the specifi ed time is earlier than the last-grab time of the most recent active grab for the client, or if the specifi ed time is later than the current X server time.

The following describes the processing that occurs depending on what constant you pass to the event-mode argument:

• If the specifi ed device is frozen by the client, event processing for that device continues as usual. If the device is frozen multiple times by the client on behalf of multiple separate grabs, AsyncThisDevice thaws for all. AsyncThisDevice has no effect if the specifi ed device is not frozen by the client, but the device need not be grabbed by the client.

- If the specifi ed device is frozen and actively grabbed by the client, event processing for that device continues normally until the next button or key event is reported to the client. At this time, the specifi ed device again appears to freeze. However, if the reported event causes the grab to be released, the specifi ed device does not freeze. SyncThisDevice has no effect if the specifi ed device is not frozen by the client or is not grabbed by the client.
- If the specifi ed device is actively grabbed by the client and is frozen as the result of an event having been sent to the client (either from the activation of a GrabDeviceButton or from a previous AllowDeviceEvents with mode SyncThisDevice, but not from a Grab), the grab is released and that event is completely reprocessed. This time, however, the request ignores any passive grabs at or above (towards the root) the grab-window of the grab just released. The request has no effect if the specifi ed device is not grabbed by the client or if it is not frozen as the result of an event.
- If the remaining devices are frozen by the client, event processing for them continues as usual. If the other devices are frozen multiple times by the client on behalf of multiple separate grabs, AsyncOtherDevices "thaws" for all. AsyncOtherDevices has no effect if the devices are not frozen by the client, but those devices need not be grabbed by the client.
- If all devices are frozen by the client, event processing (for all devices) continues normally until the next button or key event is reported to the client for a grabbed device (button event for the grabbed device, key or motion event for the device), at which time the devices again appear to freeze. However, if the reported event causes the grab to be released, then the devices do not freeze (but if any device is still grabbed, then a subsequent event for it will still cause all devices to freeze). SyncAll has no effect unless all devices are frozen by the client. If any device is frozen twice by the client on behalf of two separate grabs, SyncAll "thaws" for both (but a subsequent freeze for SyncAll will only freeze each device once).
- If all devices are frozen by the client, event processing (for all devices) continues normally. If any device is frozen multiple times by the client on behalf of multiple separate grabs, Asyn-cAll "thaws" for all. AsyncAll has no effect unless all devices are frozen by the client.

AsyncThisDevice, SyncThisDevice, and ReplayThisDevice have no effect on the processing of events from the remaining devices. AsyncOtherDevices has no effect on the processing of events from the specifi ed device. When the event\_mode is SyncAll or AsyncAll, the device parameter is ignored.

It is possible for several grabs of different devices (by the same or different clients) to be active simultaneously. If a device is frozen on behalf of any grab, no event processing is performed for the device. It is possible for a single device to be frozen because of several grabs. In this case, the freeze must be released on behalf of each grab before events can again be processed.

# **2.18.** Controlling Device Focus

The current focus window for an extension input device can be determined using the **GetDevice-Focus** request. Extension devices are focused using the **SetDeviceFocus** request in the same way that the keyboard is focused using the **SetInputFocus** request, except that a device is specified as part of the request. One additional focus state, **FollowKeyboard**, is provided for extension devices.

To get the current focus state, revert state, and focus time of an extension device, use **GetDevice-Focus**.

GetDeviceFocus

device: DEVICE

=>

focus: WINDOW, PointerRoot, FollowKeyboard, or None revert-to: Parent, PointerRoot, FollowKeyboard, or None focus-time: TIMESTAMP Errors: Device, Match

This request returns the current focus state, revert-to state, and last-focus-time of an extension device.

To set the focus of an extension device, use SetDeviceFocus.

SetDeviceFocus

device: DEVICE focus: WINDOW, PointerRoot, FollowKeyboard, or None revert-to: Parent, PointerRoot, FollowKeyboard, or None focus-time: TIMESTAMP

Errors: Device, Window, Value, Match

This request changes the focus for an extension input device and the last-focus-change-time. The request has no effect if the specified time is earlier than the last-focus-change-time or is later than the current X server time. Otherwise, the last-focus-change-time is set to the specified time, with CurrentTime replaced by the current server time.

The action taken by the server when this request is requested depends on the value of the focus argument:

- If the focus argument is **None**, all input events from this device will be discarded until a new focus window is set. In this case, the revert-to argument is ignored.
- If a window ID is assigned to the focus argument, it becomes the focus window of the device. If an input event from the device would normally be reported to this window or to one of its inferiors, the event is reported normally. Otherwise, the event is reported relative to the focus window.
- If you assign **PointerRoot** to the focus argument, the focus window is dynamically taken to be the root window of whatever screen the pointer is on at each input event. In this case, the revert-to argument is ignored.
- If you assign **FollowKeyboard** to the focus argument, the focus window is dynamically taken to be the same as the focus of the X keyboard at each input event.

The specified focus window must be viewable at the time of the request (else a **Match** error). If the focus window later becomes not viewable, the X server evaluates the revert-to argument to determine the new focus window.

- If you assign **RevertToParent** to the revert-to argument, the focus reverts to the parent (or the closest viewable ancestor), and the new revert-to value is taken to be **RevertToNone**.
- If you assign **RevertToPointerRoot**, **RevertToFollowKeyboard**, or **RevertToNone** to the revert-to argument, the focus reverts to that value.

When the focus reverts, the X server generates **DeviceFocusIn** and **DeviceFocusOut** events, but the last-focus-change time is not affected.

This request causes the X server to generate **DeviceFocusIn** and **DeviceFocusOut** events.

## 2.19. Controlling Device Feedback

To get the settings of feedbacks on an extension device, use **GetFeedbackControl**. This request provides functionality equivalent to the core **GetKeyboardControl** and **GetPointerControl** functions. It also provides a way to control displays associated with an input device that are capable of displaying an integer or string.

GetFeedbackControl device: DEVICE

=>

num\_feedbacks\_return: CARD16 return\_value: LISTofFEEDBACKSTATE

where

FEEDBACKSTATE:

{KbdFeedbackState, PtrFeedbackState, IntegerFeedbackState, StringFeedbackState, BellFeedbackState, LedFeedbackState}

Feedbacks are reported by class. Those feedbacks that are reported for the core keyboard device are in class **KbdFeedback**, and are returned in the **KbdFeedbackState** structure. The members of that structure are as follows:

CLASS Kbd:	[class: CARD8
	length: CARD16
	feedback id: CARD8
	key_click_percent: CARD8
	bell_percent: CARD8
	bell_pitch: CARD16
	bell_duration: CARD16
	led_value: BITMASK
	global_auto_repeat: {AutoRepeatModeOn, AutoRepeatMode-
	Off}
	auto_repeats: LISTofCARD8]

Those feedbacks that are equivalent to those reported for the core pointer are in feedback class **PtrFeedback** and are reported in the **PtrFeedbackState** structure. The members of that structure are:

CLASS Ptr:	[class: CARD8
	length: CARD16
	feedback id: CARD8
	accelNumerator: CARD16
	accelDenominator: CARD16
	threshold: CARD16]

Some input devices provide a means of displaying an integer. Those devices will support feedback class **IntegerFeedback**, which is reported in the **IntegerFeedbackState** structure. The members of that structure are:

CLASS Integer:	[class: CARD8
-	length: CARD16
	feedback id: CARD8
	resolution: CARD32
	min-val: INT32
	max-val: INT32]

Some input devices provide a means of displaying a string. Those devices will support feedback class **StringFeedback**, which is reported in the **StringFeedbackState** structure. The members of that structure are:

CLASS String: [class: CARD8 length: CARD16 feedback id: CARD8 max\_symbols: CARD16 num\_keysyms\_supported: CARD16 keysyms\_supported: LISTofKEYSYM]

Some input devices contain a bell. Those devices will support feedback class **BellFeedback**, which is reported in the **BellFeedbackState** structure. The members of that structure are:

CLASS Bell: [class: CARD8 length: CARD16 feedback id: CARD8 percent: CARD8 pitch: CARD16 duration: CARD16]

The percent sets the base volume for the bell between 0 (off) and 100 (loud) inclusive, if possible. Setting to -1 restores the default. Other negative values generate a **Value** error.

The pitch sets the pitch (specified in Hz) of the bell, if possible. Setting to -1 restores the default. Other negative values generate a **Value** error.

The duration sets the duration (specified in milliseconds) of the bell, if possible. Setting to -1 restores the default. Other negative values generate a **Value** error.

A bell generator connected with the console but not directly on the device is treated as if it were part of the device. Some input devices contain LEDs. Those devices will support feedback class **Led**, which is reported in the **LedFeedbackState** structure. The members of that structure are:

length: CARD16	
feedback id: CARD8	
led_mask: BITMASI	K
led_value: BITMASI	<b>X</b> ]

Each bit in led\_mask indicates that the corresponding led is supported by the feedback. At most 32 LEDs per feedback are supported. No standard interpretation of LEDs is defined.

This function will fail with a **BadMatch** error if the device specified in the request does not support feedbacks.

## Errors: Device, Match

To change the settings of a feedback on an extension device, use **ChangeFeedbackControl**.

ChangeFeedbackControl device: DEVICE feedbackid: CARD8 value-mask: BITMASK value: FEEDBACKCONTROL

Errors: Device, Match, Value

#### FEEDBACKCONTROL: {KBDFEEDBACKCONTROL, PTRFEEDBACKCONTROL, INTEGERFEEDBACKCONTROL, STRINGFEEDBACKCON-TROL, BELLFEEDBACKCONTROL, LEDFEEDBACKCON-TROL }

Feedback controls are grouped by class. Those feedbacks that are equivalent to those supported by the core keyboard are controlled by feedback class **KbdFeedbackClass** using the **KbdFeedbackControl** structure. The members of that structure are:

KBDFEEDBACKCTL:	[class: CARD8 length: CARD16 feedback id: CARD8 key_click_percent: INT8 bell_percent: INT8
	bell_pitch: INT16
	bell_duration: INT16
	led_mask: INT32
	led_value: INT32
	key: KEYCODE
	<pre>auto_repeat_mode: {AutoRepeatModeOn, AutoRepeatModeOff, AutoRepeatModeDefault}]</pre>

The key\_click\_percent sets the volume for key clicks between 0 (off) and 100 (loud) inclusive, if possible. Setting to -1 restores the default. Other negative values generate a **Value** error.

If both auto\_repeat\_mode and key are specified, then the auto\_repeat\_mode of that key is changed, if possible. If only auto\_repeat\_mode is specified, then the global auto-repeat mode for the entire keyboard is changed, if possible, without affecting the per-key settings. It is a **Match** error if a key is specified without an auto\_repeat\_mode.

The order in which controls are verified and altered is server-dependent. If an error is generated, a subset of the controls may have been altered.

Those feedback controls equivalent to those of the core pointer are controlled by feedback class **PtrFeedbackClass** using the **PtrFeedbackControl** structure. The members of that structure are as follows:

PTRFEEDBACKCTL:	[class: CARD8
	length: CARD16
	feedback id: CARD8
	accelNumerator: INT16
	accelDenominator: INT16
	threshold: INT16]

The acceleration, expressed as a fraction, is a multiplier for movement. For example, specifying 3/1 means the device moves three times as fast as normal. The fraction may be rounded arbitrarily by the X server. Acceleration only takes effect if the device moves more than threshold pixels at once and only applies to the amount beyond the value in the threshold argument. Setting a value to -1 restores the default. The values of the do-accel and do-threshold arguments must be nonzero for the device values to be set. Otherwise, the parameters will be unchanged. Negative values generate a **Value** error, as does a zero value for the accel-denominator argument.

Some devices are capable of displaying an integer. This is done using feedback class **Inte-gerFeedbackClass** using the **IntegerFeedbackControl** structure. The members of that structure are as follows:

INTEGERCTL:	[class: CARD8
	length: CARD16
	feedback id: CARD8
	int_to_display: INT32]

Some devices are capable of displaying an string. This is done using feedback class **StringFeed**-**backClass** using the **StringFeedbackCtl** structure. The members of that structure are as follows:

STRINGCTL: [class: CARD8 length: CARD16 feedback id: CARD8 syms\_to\_display: LISTofKEYSYMS]

Some devices contain a bell. This is done using feedback class **BellFeedbackClass** using the **BellFeedbackControl** structure. The members of that structure are as follows:

BELLCTL: [class: CARD8 length: CARD16 feedback id: CARD8 percent: INT8 pitch: INT16 duration: INT16]

Some devices contain leds. These can be turned on and off using the LedFeedbackControl structure. The members of that structure are as follows:

LEDCTL: [class: CARD8 length: CARD16 feedback id: CARD8 led\_mask: BITMASK led\_value: BITMASK]

Errors: Device, Match, Value

## 2.20. Ringing a Bell on an Input Device

To ring a bell on an extension input device, use **DeviceBell**.

DeviceBell

device: DEVICE feedbackclass: CARD8 feedbackid: CARD8 percent: INT8

Errors: Device, Value

This request is analogous to the core **Bell** request. It rings the specifi ed bell on the specifi ed input device feedback, using the specifi ed volume. The specifi ed volume is relative to the base volume for the feedback. If the value for the percent argument is not in the range -100 to 100 inclusive, a **Value** error results. The volume at which the bell rings when the percent argument is nonnegative is:

base - [(base \* percent) / 100] + percent

The volume at which the bell rings when the percent argument is negative is:

base + [(base \* percent) / 100]

To change the base volume of the bell, use ChangeFeedbackControl request.

## 2.21. Controlling Device Encoding

To get the keyboard mapping of an extension device that has keys, use GetDeviceKeyMapping.

GetDeviceKeyMapping

device: DEVICE fi rst-keycode: KEYCODE count: CARD8

=>

keysyms-per-keycode: CARD8 keysyms: LISTofKEYSYM

Errors: Device, Match, Value

This request returns the symbols for the specifi ed number of keycodes for the specifi ed extension device, starting with the specifi ed keycode. The fi rst-keycode must be greater than or equal to min-keycode as returned in the connection setup (else a **Value** error), and

fi rst-keycode + count -1

must be less than or equal to max-keycode as returned in the connection setup (else a Value error). The number of elements in the keysyms list is

count \* keysyms-per-keycode

and KEYSYM number N (counting from zero) for keycode K has an index (counting from zero) of

(K - fi rst-keycode) \* keysyms-per-keycode + N

in keysyms. The keysyms-per-keycode value is chosen arbitrarily by the server to be large enough to report all requested symbols. A special KEYSYM value of **NoSymbol** is used to fill in unused elements for individual keycodes.

If the specified device has not first been opened by this client via **OpenDevice**, or if that device does not support input class Keys, this request will fail with a **Device** error.

To change the keyboard mapping of an extension device that has keys, use **ChangeDe**viceKeyMapping.

ChangeDeviceKeyMapping device: DEVICE fi rst-keycode: KEYCODE keysyms-per-keycode: CARD8 keysyms: LISTofKEYSYM num\_codes: CARD8

Errors: Device, Match, Value, Alloc

## X Input Extension Protocol Specification

This request is analogous to the core **ChangeKeyMapping** request. It defines the symbols for the specifi ed number of keycodes for the specifi ed extension device. If the specifi ed device has not first been opened by this client via **OpenDevice**, or if that device does not support input class Keys, this request will fail with a **Device** error.

The number of elements in the keysyms list must be a multiple of keysyms\_per\_keycode. Otherwise, **ChangeDeviceKeyMapping** generates a **Length** error. The specified first\_keycode must be greater than or equal to the min\_keycode value returned by the **ListInputDevices** request, or this request will fail with a **Value** error. In addition, if the following expression is not less than the max\_keycode value returned by the **ListInputDevices** request, the request will fail with a **Value** error:

fi rst\_keycode + (num\_codes / keysyms\_per\_keycode) - 1

To obtain the keycodes that are used as modifilers on an extension device that has keys, use **Get-DeviceModifi erMapping**.

GetDeviceModifi erMapping device: DEVICE

=>

keycodes-per-modifi er: CARD8 keycodes: LISTofKEYCODE

Errors: Device, Match

This request is analogous to the core **GetModifi erMapping** request. This request returns the keycodes of the keys being used as modifi ers. The number of keycodes in the list is 8\*keycodes-per-modifi er. The keycodes are divided into eight sets, with each set containing keycodes-per-modifi er elements. The sets are assigned in order to the modifi ers **Shift, Lock, Control, Mod1**, **Mod2**, **Mod3**, **Mod4**, and **Mod5**. The keycodes-per-modifi er value is chosen arbitrarily by the server; zeroes are used to fill in unused elements within each set. If only zero values are given in a set, the use of the corresponding modifi er has been disabled. The order of keycodes within each set is chosen arbitrarily by the server.

To set which keycodes that are to be used as modifiers for an extension device, use **SetDevice-ModifierMapping**.

SetDeviceModifi erMapping

device: DEVICE keycodes-per-modifi er: CARD8 keycodes: LISTofKEYCODE

=>

status: {Success, Busy, Failed}

Errors: Device, Match, Value, Alloc

This request is analogous to the core **SetModifi erMapping** request. This request specifi es the keycodes (if any) of the keys to be used as modifi ers. The number of keycodes in the list must be 8\*keycodes-per-modifi er (else a **Length** error). The keycodes are divided into eight sets, with the sets, with each set containing keycodes-per-modifi er elements. The sets are assigned in order to the modifi ers **Shift**, **Lock**, **Control**, **Mod1**, **Mod2**, **Mod3**, **Mod4**, and **Mod5**. Only non-zero keycode values are used within each set; zero values are ignored. All of the non-zero keycodes must be in the range specifi ed by min-keycode and max-keycode in the **ListInputDevices** request

### X Input Extension Protocol Specifi cation

(else a **Value** error). The order of keycodes within a set does not matter. If no non-zero values are specified in a set, the use of the corresponding modifier is disabled, and the modifier bit will always be zero. Otherwise, the modifier bit will be one whenever at least one of the keys in the corresponding set is in the down position.

A server can impose restrictions on how modifiers can be changed (for example, if certain keys do not generate up transitions in hardware or if multiple keys per modifier are not supported). The status reply is **Failed** if some such restriction is violated, and none of the modifiers are changed.

If the new non-zero keycodes specified for a modifier differ from those currently defined, and any (current or new) keys for that modifier are logically in the down state, then the status reply is **Busy**, and none of the modifiers are changed.

This request generates a DeviceMappingNotify event on a **Success** status. The **DeviceMappingNotify** event will be sent only to those clients that have expressed an interest in receiving that event via the **XSelectExtensionEvent** request.

A X server can impose restrictions on how modifi ers can be changed, for example, if certain keys do not generate up transitions in hardware or if multiple modifi er keys are not supported. If some such restriction is violated, the status reply is **MappingFailed**, and none of the modifi ers are changed. If the new keycodes specifi ed for a modifi er differ from those currently defi ned and any (current or new) keys for that modifi er are in the logically down state, the status reply is **Map-pingBusy**, and none of the modifi ers are changed.

#### 2.22. Controlling Button Mapping

These requests are analogous to the core **GetPointerMapping** and **ChangePointerMapping** requests. They allow a client to determine the current mapping of buttons on an extension device, and to change that mapping.

To get the current button mapping for an extension device, use GetDeviceButtonMapping.

```
GetDeviceButtonMapping
device: DEVICE
nmap: CARD8
```

=>

map\_return: LISTofCARD8

Errors: Device, Match

The **GetDeviceButtonMapping** function returns the current mapping of the buttons on the specifi ed device. Elements of the list are indexed starting from one. The length of the list indicates the number of physical buttons. The nominal mapping is the identity mapping map[i]=i.

**nmap** indicates the number of elements in the **map\_return** array. Only the first nmap entries will be copied by the library into the map\_return array.

To set the button mapping for an extension device, use SetDeviceButtonMapping.

SetDeviceButtonMapping device: DEVICE map: LISTofCARD8 nmap: CARD8

=>

status: CARD8

Errors: Device, Match, Value

The **SetDeviceButtonMapping** function sets the mapping of the specified device and causes the X server to generate a **DeviceMappingNotify** event on a status of **MappingSuccess**. Elements of the list are indexed starting from one. The length of the list, specified in **nmap**, must be the same as **GetDeviceButtonMapping** would return. Otherwise, **SetDeviceButtonMapping** generates a **Value** error. A zero element disables a buttons, and elements are not restricted in value by the number of physical buttons. However, no two elements can have the same nonzero value. Otherwise, this function generates a **Value** error. If any of the buttons to be altered are in the down state, the status reply is **MappingBusy** and the mapping is not changed.

#### 2.23. Obtaining The State Of A Device

To obtain vectors that describe the state of the keys, buttons and valuators of an extension device, use **QueryDeviceState**.

QueryDeviceState device: DEVICE

=>

device-id: CARD8 data: LISTofINPUTCLASS

where

INPUTCLASS:	{VALUATOR, BUTTON, KEY}
CLASS VALUATOR:	[class: CARD8 num_valuators: CARD8 mode: CARD8 #x01 device mode (0 = Relative, 1 = Absolute) #x02 proximity state (0 = InProximity, 1 = OutOfProximity) valuators: LISTofINT32]
CLASS BUTTON:	[class: CARD8 num_buttons: CARD8 buttons: LISTofCARD8]
CLASS KEY:	[class: CARD8 num_keys: CARD8 keys: LISTofCARD8]

Errors: Device

The **QueryDeviceState** request returns the current logical state of the buttons, keys, and valuators on the specifi ed input device. The *buttons* and *keys* arrays, byte N (from 0) contains the bits for key or button 8N to 8N+7 with the least signifi cant bit in the byte representing key or button 8N.

If the device has valuators, a bit in the mode fi eld indicates whether the device is reporting Absolute or Relative data. If it is reporting Absolute data, the valuators array will contain the current value of the valuators. If it is reporting Relative data, the valuators array will contain undefi ned data.

If the device reports proximity information, a bit in the mode field indicates whether the device is InProximity or OutOfProximity.

## 3. Events

The input extension creates input events analogous to the core input events. These extension input events are generated by manipulating one of the extension input devices.

## 3.1. Button, Key, and Motion Events

DeviceKeyPress DeviceKeyRelease DeviceButtonPress, DeviceButtonRelease DeviceMotionNotify

> device: CARD8 root, event: WINDOW child: Window or None same-screen: BOOL root-x, root-y, event-x, event-y: INT16 detail: <see below> state: SETofKEYBUTMASK time: TIMESTAMP

These events are generated when a key, button, or valuator logically changes state. The generation of these logical changes may lag the physical changes, if device event processing is frozen. Note that **DeviceKeyPress** and **DeviceKeyRelease** are generated for all keys, even those mapped to modifi er bits. The "source" of the event is the window the pointer is in. The window with respect to which the event is normally reported is found by looking up the hierarchy (starting with the source window) for the fi rst window on which any client has selected interest in the event. The actual window used for reporting can be modified by active grabs and by the focus window. The window the event is reported with respect to is called the "event" window.

The root is the root window of the "source" window, and root-x and root-y are the pointer coordinates relative to root's origin at the time of the event. Event is the "event" window. If the event window is on the same screen as root, then event-x and event-y are the pointer coordinates relative to the event window's origin. Otherwise, event-x and event-y are zero. If the source window is an inferior of the event window, then child is set to the child of the event window that is an ancestor of (or is) the source window. Otherwise, it is set to None. The state component gives the logical state of the buttons on the core X pointer and modifi er keys on the core X keyboard just before the event. The detail component type varies with the event type:

Event	Component
DeviceKeyPress,	KEYCODE
DeviceKeyRelease	
DeviceButtonPress,	BUTTON
DeviceButtonRelease	
DeviceMotionNotify	{ Normal , Hint }

The granularity of motion events is not guaranteed, but a client selecting for motion events is guaranteed to get at least one event when a valuator changes. If **DeviceMotionHint** is selected, the server is free to send only one **DeviceMotionNotify** event (with detail **Hint**) to the client for the event window, until either a key or button changes state, the pointer leaves the event window, or the client issues a **QueryDeviceState** or **GetDeviceMotionEvents** request.

# **3.2.** DeviceValuator Event

**DeviceValuator** 

device: CARD8 device\_state: SETofKEYBUTMASK num\_valuators: CARD8 fi rst\_valuator: CARD8 valuators: LISTofINT32

DeviceValuator events are generated to contain valuator information for which there is insufficient space in DeviceKey, DeviceButton, DeviceMotion, and Proximity wire events. For events of these types, a second event of type DeviceValuator follows immediately. The library combines these events into a single event that a client can receive via XNextEvent. DeviceValuator events are not selected for by clients, they only exist to contain information that will not fit into some event selected by clients.

The device\_state component gives the state of the buttons and modifiers on the device generating the event.

Extension motion devices may report motion data for a variable number of axes. The valuators array contains the values of all axes reported by the device. If more than 6 axes are reported, more than one DeviceValuator event will be sent by the server, and more than one DeviceKey, DeviceButton, DeviceMotion, or Proximity event will be reported by the library. Clients should examine the corresponding fi elds of the event reported by the library to determine the total number of axes reported, and the fi rst axis reported in the current event. Axes are numbered beginning with zero.

For Button, Key and Motion events on a device reporting absolute motion data the current value of the device's valuators is reported. For devices that report relative data, Button and Key events may be followed by a DeviceValuator event that contains 0s in the num\_valuators fi eld. In this case, only the device\_state component will have meaning.

## **3.3. Device Focus Events**

DeviceFocusIn DeviceFocusOut

device: CARD8 time: TIMESTAMP event: WINDOW mode: { Normal, WhileGrabbed, Grab, Ungrab} detail: { Ancestor, Virtual, Inferior, Nonlinear, NonlinearVirtual, Pointer, PointerRoot, None}

These events are generated when the input focus changes and are reported to clients selecting **DeviceFocusChange** for the specifi ed device and window. Events generated by **SetDeviceFocus** when the device is not grabbed have mode **Normal**. Events generated by **SetDeviceFocus** when the device is grabbed have mode **WhileGrabbed**. Events generated when a device grab actives have mode **Grab**, and events generated when a device grab deactivates have mode **Ungrab**.

All **DeviceFocusOut** events caused by a window unmap are generated after any **UnmapNotify** event, but the ordering of **DeviceFocusOut** with respect to generated **EnterNotify**, **LeaveNotify**, **VisibilityNotify** and **Expose** events is not constrained.

**DeviceFocusIn** and **DeviceFocusOut** events are generated for focus changes of extension devices in the same manner as focus events for the core devices are generated.

# **3.4.** Device State Notify Event

DeviceStateNotify

```
time: TIMESTAMP
device: CARD8
num keys: CARD8
num buttons: CARD8
num valuators: CARD8
classes_reported: CARD8 {SetOfDeviceMode | SetOfInputClass}
       SetOfDeviceMode:
               #x80 ProximityState
                       0 = \text{InProxmity}, 1 = \text{OutOfProximity}
               #x40 Device Mode
                       (0 = \text{Relative}, 1 = \text{Absolute})
       SetOfInputClass:
               #x04 reporting valuators
               #x02 reporting buttons
               #x01 reporting keys
buttons: LISTofCARD8
keys: LISTofCARD8
valuators: LISTofCARD32
```

This event reports the state of the device just as in the **QueryDeviceState** request. This event is reported to clients selecting **DeviceStateNotify** for the device and window and is generated immediately after every **EnterNotify** and **DeviceFocusIn**. If the device has no more than 32 buttons, no more than 32 keys, and no more than 3 valuators, This event can report the state of the device. If the device has more than 32 buttons, the event will be immediately followed by a DeviceButtonStateNotify event. If the device has more than 32 keys, the event will be followed by a DeviceKeyStateNotify event. If the device has more than 3 valuators, the event will be followed by one or more DeviceValuator events.

#### **3.5.** Device KeyState and ButtonState Notify Events

DeviceKeyStateNotify

device: CARD8 keys: LISTofCARD8

DeviceButtonStateNotify

device: CARD8 buttons: LISTofCARD8

These events contain information about the state of keys and buttons on a device that will not fit into the DeviceStateNotify wire event. These events are not selected by clients, rather they may immediately follow a DeviceStateNotify wire event and be combined with it into a single DeviceStateNotify client event that a client may receive via XNextEvent.

#### **3.6.** DeviceMappingNotify Event

**DeviceMappingNotify** 

time: TIMESTAMP device: CARD8 request: CARD8 fi rst\_keycode: CARD8 count: CARD8

This event reports a change in the mapping of keys, modifilers, or buttons on an extension device. This event is reported to clients selecting **DeviceMappingNotify** for the device and window and is generated after every client **SetDeviceButtonMapping**, **ChangeDeviceKeyMapping**, or **ChangeDeviceModifi erMapping** request.

# 3.7. ChangeDeviceNotify Event

ChangeDeviceNotify

device: CARD8 time: TIMESTAMP request: CARD8

This event reports a change in the physical device being used as the core X keyboard or X pointer device. **ChangeDeviceNotify** events are reported to clients selecting **ChangeDeviceNotify** for the device and window and is generated after every client **ChangeKeyboardDevice** or **Change-PointerDevice** request.

## 3.8. Proximity Events

ProximityIn ProximityOut

> device: CARD8 root, event: WINDOW child: Window or None same-screen: BOOL root-x, root-y, event-x, event-y: INT16 state: SETofKEYBUTMASK time: TIMESTAMP device-state: SETofKEYBUTMASK axis-count: CARD8 fi rst-axis: CARD8 axis-data: LISTofINT32

These events are generated by some devices (such as graphics tablets or touchscreens) to indicate that a stylus has moved into or out of contact with a positional sensing surface.

The "source" of the event is the window the pointer is in. The window with respect to which the event is normally reported is found by looking up the hierarchy (starting with the source window) for the first window on which any client has selected interest in the event. The actual window used for reporting can be modified by active grabs and by the focus window. The window the event is reported with respect to is called the "event" window.

The root is the root window of the "source" window, and root-x and root-y are the pointer coordinates relative to root's origin at the time of the event. Event is the "event" window. If the event window is on the same screen as root, then event-x and event-y are the pointer coordinates relative to the event window's origin. Otherwise, event-x and event-y are zero. If the source window is an inferior of the event window, then child is set to the child of the event window that is an ancestor of (or is) the source window. Otherwise, it is set to None. The state component gives the logical state of the buttons on the core X pointer and modifi er keys on the core X keyboard just before the event. The device-state component gives the state of the buttons and modifi ers on the device generating the event.

# Appendix A

# **Input Extension Protocol Encoding**

#### **Syntactic Conventions**

All numbers are in decimal, unless prefixed with #x, in which case they are in hexadecimal (base 16). The general syntax used to describe requests, replies, errors, events, and compound types is:

NameofThing encode-form

encode-form

Each encode-form describes a single component. For components described in the protocol as:

name: TYPE

the encode-form is:

1

TYPE name

N is the number of bytes occupied in the data stream, and TYPE is the interpretation of those bytes. For example,

depth: CARD8

becomes:

CARD8 depth

For components with a static numeric value the encode-form is:

N value name

The value is always interpreted as an N-byte unsigned integer. For example, the first two bytes of a Window error are always zero (indicating an error in general) and three (indicating the Window error in particular):

1 0 Error 1 3 code

For components described in the protocol as:

name: {Name1, ..., NameI}

the encode-form is:

Ν

name value1 Name1

valueI NameI

...

The value is always interpreted as an N-byte unsigned integer. Note that the size of N is sometimes larger than that strictly required to encode the values. For example:

#### class: {InputOutput, InputOnly, CopyFromParent}

becomes:

2			class
	0	CopyFromParent	
	1	InputOutput	
	2	InputOnly	

For components described in the protocol as:

#### NAME: TYPE or Alternative1 ... or AlternativeI

the encode-form is:

TYPE value1	Alternative1	NAME
 valueI	AlternativeI	

The alternative values are guaranteed not to conflict with the encoding of TYPE. For example:

#### destination: WINDOW or PointerWindow or InputFocus

becomes:

4	WIND	OW	destination
	0	PointerWindow	
	1	InputFocus	

For components described in the protocol as:

#### value-mask: BITMASK

the encode-form is:

Ν	BITMASK mask1 mask-name1		value-mask
	 maskI	mask-nameI	

The individual bits in the mask are specified and named, and N is 2 or 4. The most-significant bit in a BITMASK is reserved for use in defining chained (multiword) bitmasks, as extensions augment existing core requests. The precise interpretation of this bit is not yet defined here, although a probable mechanism is that a 1-bit indicates that another N bytes of bitmask follows, with bits within the overall mask still interpreted from least-significant to most-significant with an N-byte unit, with N-byte units interpreted in stream order, and with the overall mask being byte-swapped in individual N-byte units.

For LISTofVALUE encodings, the request is followed by a section of the form:

VALUEs encode-form ... encode-form

listing an encode-form for each VALUE. The NAME in each encode-form keys to the corresponding BITMASK bit. The encoding of a VALUE always occupies four bytes, but the number of bytes specified in the encoding-form indicates how many of the least-significant bytes are actually used; the remaining bytes are unused and their values do not matter.

In various cases, the number of bytes occupied by a component will be specified by a lowercase single-letter variable name instead of a specific numeric value, and often some other component will have its value specified as a simple numeric expression involving these variables. Components specified with such expressions are always interpreted as unsigned integers. The scope of such variables is always just the enclosing request, reply, error, event, or compound type structure. For example:

2	3+n	request length
4n	LISTofPOINT	points

For unused bytes (the values of the bytes are undefined and do not matter), the encode-form is:

N unused

If the number of unused bytes is variable, the encode-form typically is:

р

unused, p=pad(E)

where E is some expression, and pad(E) is the number of bytes needed to round E up to a multiple of four.

 $pad(E) = (4 - (E \mod 4)) \mod 4$ 

# **Common Types**

LISTofFOO

In this document the LIST of notation strictly means some number of repetitions of the FOO encoding; the actual length of the list is encoded elsewhere.

#### SETofFOO

A set is always represented by a bitmask, with a 1-bit indicating presence in the set.

BITMASK: CARD32 WINDOW: CARD32 BYTE: 8-bit value INT8: 8-bit signed integer INT16: 16-bit signed integer INT32: 32-bit signed integer CARD8: 8-bit unsigned integer CARD16: 16-bit unsigned integer TIMESTAMP: CARD32 EVENTCLASS: CARD32

### INPUTCLASS

0 1 2 3 4 5 6	KeyClass ButtonClass ValuatorClass FeedbackClass ProximityClass FocusClass OtherClass
INPUTCLASS	
0	KbdFeedbackClass
1	PtrFeedbackClass
2 3	StringFeedbackClass IntegerFeedbackClass
4	LedFeedbackClass
5	BellFeedbackClass
INPUTINFO 0	KEYINFO
1	BUTTONINFO
2	VALUATORINFO
DEVICEMODE	
0	Relative
1	Absolute
PROXIMITYSTATE	
0	InProximity
1	OutOfProximity
BOOL	
0	False
1	True
KEYSYM: CARD32	
KEYCODE: CARD8	
BUTTON: CARD8	

# SETofKEYBUTMASK

Shift
Lock
Control
Mod1
Mod2
Mod3
Mod4
Mod5
Button1
Button2
Button3
Button4
Button5
unused but must be zero

#### SETofKEYMASK

encodings are the same as for SETofKEYBUTMASK, except with #xff00 unused but must be zero

length of name in bytes

name

#### STRING8: LISTofCARD8

#### STR

1	n
n	STRING8

# **Errors**

#### Request

quest		
1	0	Error
1	1	code
2	CARD16	sequence number
4		unused
2	CARD16	minor opcode
1	CARD8	major opcode
21		unused

# Value

1	0	Error
1	2	code
2	CARD16	sequence number
4	<32-bits>	bad value
2	CARD16	minor opcode
1	CARD8	major opcode
21		unused

#### Window

1	0	Error
1	3	code
2	CARD16	sequence number
4	CARD32	bad resource id
2	CARD16	minor opcode
1	CARD8	major opcode
21		unused

Match 1 2 4 2 1 21	0 8 CARD16 CARD16 CARD8	Error code sequence number unused minor opcode major opcode unused
Access 1 1 2 4 2 1 21	0 10 CARD16 CARD16 CARD8	Error code sequence number unused minor opcode major opcode unused
Alloc 1 1 2 4 2 1 21	0 11 CARD16 CARD16 CARD8	Error code sequence number unused minor opcode major opcode unused
Name 1 2 4 2 1 21	0 15 CARD16 CARD16 CARD8	Error code sequence number unused minor opcode major opcode unused
Device 1 1 2 4 2 1 21	0 CARD8 CARD16 CARD16 CARD8	Error code sequence number unused minor opcode major opcode unused
Event 1 2 4 2 1 21	0 CARD8 CARD16 CARD16 CARD8	Error code sequence number unused minor opcode major opcode unused

37

Mode		
1	0	Error
1	CARD8	code
2	CARD16	sequence number
4		unused
2	CARD16	minor opcode
1	CARD8	major opcode
21		unused

# Class

1	0	Error
1	CARD8	code
2	CARD16	sequence number
4		unused
2	CARD16	minor opcode
1	CARD8	major opcode
21		unused

# Keyboards

KEYCODE values are always greater than 7 (and less than 256).

KEYSYM values with the bit #x10000000 set are reserved as vendor-specific.

The names and encodings of the standard KEYSYM values are contained in appendix F.

# Pointers

BUTTON values are numbered starting with one.

# Requests

GetExtensionVersion

1 1 2 2 2 n p	CARD8 1 2+(n+p)/4 n STRING8	input extension opcode GetExtensionVersion opcode request length length of name unused name unused, p=pad(n)
=> 1 1 2 4 2 2 1 19	1 1 CARD16 0 CARD16 CARD16 BOOL	Reply GetExtensionVersion opcode sequence number reply length major version minor version present unused
ListInpu 1 1 2	ntDevices CARD8 2 1	input extension opcode ListInputDevices opcode request length
=> 1 1 2 4 1 23 n p	1 2 CARD16 (n+p)/4 CARD8 LISTofDEVICEINFO	Reply ListInputDevices opcode sequence number reply length number of input devices unused info for each input device unused, p=pad(n)

	CEINFO CARD32 CARD8 CARD8 CARD8 LISTofINPUTINF STR	0 1 2 FO	device type device id number of input cla device use IsXPointer IsXKeyboard IsXExtensionDevic unused input info for each name unused, p=pad(m)	
INPUT	INFO	KEYINFO or BUT	TONINFO or VAL	UATORINFO
KEYIN 1 1 1 2 2	IFO 0 8 KEYCODE KEYCODE CARD16		class id length minimum keycode maximum keycode number of keys unused	
BUTTO 1 1 2	NINFO 1 4 CARD16		class id length number of buttons	
1 1 1	TORINFO 2 8+12n n SETofDEVIG CARD32 LISTofAXIS		class id length number o mode size of m valuator	otion buffer
AXISIN 4 4 4	CARD32 CARD32 CARD32		resolution minimum value maximum value	
OpenDe 1 2 1 3	CARD8 3 2 CARD8		input extension op OpenDevice opcod request length device id unused	code le
=> 1 1 2 4 1 23 n p	1 3 CARD16 (n+p)/4 CARD8 LISTofINPUTCL	ASSINFO		Reply OpenDevice opcode sequence number reply length number of input classes unused input class information unused, p=pad(n)

INPUT 1	CLASSINFO CARD8 0 1 2 3 4 5	KEY BUTTON VALUATOR FEEDBACK PROXIMITY FOCUS	input class id	
1	6 CARD8	OTHER	event type base co	de for this class
CloseDe 1 1 2 1 3	vice CARD8 4 2 CARD8		input extension op CloseDevice opcor request length device id unused	
SetDevia 1 2 1 1 2 2	ceMode CARD8 5 2 CARD8 CARD8		input extension op SetDeviceMode op request length device id mode unused	
=> 1 2 4 1 23	1 5 CARD16 0 CARD8 0 3 + fi rst_error	l DeviceBusy		Reply SetDeviceMode opcode sequence number reply length status Success AlreadyGrabbed unused
SelectEx 1 2 4 2 2 4n	ttensionEvent CARD8 6 3+n Window CARD16 LISTofEVENTCL	ASS	input extension op SelectExtensionEv request length event window count unused desired events	
GetSelec 1 2 4	ctedExtensionEvents CARD8 7 2 Window	i	input extension op GetSelectedExtens request length event window	code sionEvents opcode

=>				
1	1		Reply	
1	7		GetSelecteExtensi	ionEvents opcode
2	CARD16		sequence number	
4	n + m		reply length	
2	n		this client count	
2	m		all clients count	
20			unused	
4n	LISTOFEVENTCL		this client list	
4m	LISTofEVENTCL	.ASS	all clients list	
ChangeI	DeviceDontPropagat	teList		
1	CARD8		input extension op	
1	8			ntPropagateList opcode
2	3+n		request length	
4 2	Window		event window	
2 1	n		count of events	
1	mode	AddToList		
	0 1	DeleteFromList		
1	1	DeleterTomList	unused	
4n	LISTofEVENTCL	ASS	desired events	
	EIGTOIL (EITTOL		desired events	
с. р. ·				
	ceDontPropagateLis	st	· , , ·	
1	CARD8 9		input extension op	opagateList opcode
2	2		request length	opagateList opcode
4	2 Window		event window	
4	willdow		event window	
=>				
	1		Reply	
1	9			opagateList opcode
2	CARD16		sequence number	opuguteEnst opeoue
4	n		reply length	
2	n		count of events	
22			unused	
4n	LISTofEVENTCL	ASS	don't propagate lis	st
GetDevi	ceMotionEvents			
1	CARD8		input extension op	ocode
1	10		GetDeviceMotion	
2	4		request length	
4	TIMESTAMP		start	
	0	CurrentTime		
4	TIMESTAMP		stop	
	0	CurrentTime		
1	CARD8		device id	
3			unused	
=>				
1		1		Reply
1		10		GetDeviceMotionEvents opcode
2		CARD16		sequence number
4		(m+1)n		reply length
4		n m		number of DEVICETIMECOORDs in events
1		m CARD8		number of valuators per event mode of the device
1		0		Absolute
		1		Relative
18		-		unused
	+4)n	LISTofDEVICET	IMECOORD	events
(				

4	ETIMECOORD TIMESTAMP LISTofINT32		time valuators
Changek 1 2 1 3	KeyboardDevice CARD8 11 2 CARD8		input extension opcode ChangeKeyboardDevice opcode request length device id unused
=> 1 1 2 4 1 23	1 11 CARD16 0 1 2	Success AlreadyGrabbed DeviceFrozen	Reply ChangeKeyboardDevice opcode sequence number reply length status unused
ChangeF 1 2 1 1 1 1 1	PointerDevice CARD8 12 2 CARD8 CARD8 CARD8 CARD8		input extension opcode ChangePointerDevice opcode request length x-axis y-axis device id unused
=> 1 2 4 1 23	1 12 CARD16 0 1 2	Success AlreadyGrabbed DeviceFrozen	Reply ChangePointerDevice opcode sequence number reply length status unused
GrabDev 1 2 4 4	vice CARD8 13 5+n WINDOW TIMESTAMP 0	CurrentTime	input extension opcode GrabDevice opcode request length grab-window time
2 1	n 0	Synchronous	count of events this-device-mode
1	1 0 1	Asynchronous Synchronous Asynchronous	other-devices-mode
1 1 2 4n	BOOL CARD8 LISTofEVENTCL/		owner-events device id unused event list

=> 1 2 4 1 23	1 13 CARD16 0 0 1 2 3 4	Success AlreadyGrabbed InvalidTime NotViewable Frozen	Reply GrabDevice opcode sequence number reply length status
UngrabI 1 2 4 1 3	Device CARD8 14 3 TIMESTAMP 0 CARD8	CurrentTime	input extension opcode UngrabDevice opcode request length time device id unused
GrabDev 1 2 4 2 2 1 1 1 1 1 1 2 4n	viceKey CARD8 15 5+n WINDOW n SETofKEYMASK #x8000 CARD8 #x0FF CARD8 KEYCODE 0 0 1 0 1 BOOL LISTofEVENTCL/	AnyModifi er UseXKeyboard AnyKey Synchronous Asynchronous Asynchronous	input extension opcode GrabDeviceKey opcode request length grab-window count of events modifi er device grabbed device key this-device-mode other-devices-mode
UngrabE 1 2 4 2 1 1 1 3	DeviceKey CARD8 16 4 WINDOW SETofKEYMASK #x8000 CARD8 #x0FF KEYCODE 0 CARD8	AnyModifi er UseXKeyboard AnyKey	input extension opcode UngrabDeviceKey opcode request length grab-window modifi ers modifi er device key grabbed device unused

43

	·		
GrabDe	viceButton CARD8		input automaion oncodo
1	17		input extension opcode GrabDeviceButton opcode
2	5+n		request length
4	WINDOW		grab-window
4	CARD8		grabbed device
1	CARD8		modifi er device
1		UseVVerboard	mount er device
C	#x0FF	UseXKeyboard	accurate of designed execute
2 2	n Set-freymaer		count of desired events
	SETofKEYMASK		modifi ers
1	0	0 1	this-device-mode
	0	Synchronous	
1	1	Asynchronous	4 1
1	0	0 1	other-device-mode
	0	Synchronous	
	1	Asynchronous	•
1	BUTTON		button
	0	AnyButton	
1	BOOL		owner-events
	#x8000	AnyModifi er	
2			unused
4n	LISTofEVENTCL	ASS	event list
Ungrahl	DeviceButton		
1	CARD8		input extension opcode
1	18		UngrabDeviceButton opcode
2	4		request length
4	WINDOW		grab-window
2	SETofKEYMASK		modifiers
2	#x8000	AnyModifi er	mouniers
1	CARD8	7 my wiodin ei	modifi er device
1	#x0FF	UseXKeyboard	mount et device
1	BUTTON	USCARCyboard	button
1	0	AnyDutton	button
1	CARD8	AnyButton	graphed davias
3	CARDo		grabbed device unused
3			unused
AllowD	eviceEvents		
1	CARD8		input extension opcode
1	19		AllowDeviceEvents opcode
2	3		request length
4	TIMESTAMP		time
	0	CurrentTime	
1			mode
	0	AsyncThisDevice	
	1	SyncThisDevice	
	2	ReplayThisDevice	
	3	AsyncOtherDevice	S
	4	AsyncAll	5
	5	SyncAll	
1	CARD8	_ ;	device id
2	CIMDO		unused
2			unuseu
GetDev	iceFocus		
1	CARD8		input extension opcode
1	20		GetDeviceFocus opcode
2	2		request length
1	CARD8		device
3			unused

=> 1 1 2 4 4	1	None PointerRoot FollowKeyboard	Reply GetDeviceFocus opcode sequence number reply length focus
4 1 15	TIMESTAMP 0 1 2	focus time None PointerRoot Parent FollowKeyboard	revert-to unused
15			unused
SetDevia 1 2 4 4 1 1 2 4	CARD8 21 4 WINDOW 0 1 3 TIMESTAMP 0 0 1 2	None PointerRoot FollowKeyboard CurrentTime None PointerRoot Parent FollowKeyboard	input extension opcode SetDeviceFocus opcode request length focus time revert-to device unused
GetFeed 1 2 1 3	backControl CARD8 22 2 CARD8		input extension opcode GetFeedbackControl opcode request length device id unused
=> 1 1 2 4 2 22 m	1 22 CARD16 m/4 n LISTofFEEDBACK	STATE	Reply GetFeedbackControl opcode sequence number reply length number of feedbacks supported unused feedbacks

FEEDBACKSTATE KBDFEEDBACKSTATE, PTRFEEDBACKSTATE, INTEGERFEEDBACKSTATE, STRINGFEEDBACKSTATE, BELLFEEDBACKSTATE, or LEDFEEDBACKSTATE

#### KBDFEEDBACKSTATE

1	0		feedback class id
1	CARD8		id of this feedback
2	20		length
2	CARD16		pitch
2	CARD16		duration
4	CARD32		led_mask
4	CARD32		led_values
1			global_auto_repeat
	0	Off	
	1	On	
1	CARD8		click
1	CARD8		percent
1			unused
32	LISTofCARD8	auto_repeats	

#### PTRFEEDBACKSTATE

1	0	feedback class id
1	CARD8	id of this feedback
2	12	length
2		unused
2	CARD16	acceleration-numerator
2	CARD16	acceleration-denominator
2	CARD16	threshold

#### INTEGERFEEDBACKSTATE

1	0
1	CADDO

- 1 CARD8
- 2 16 4 CARD32
- 4 CARD32 4 INT32
- 4 INT32 4 INT32

# STRINGFEEDBACKSTATE

- 1 1
- 1 CARD8
- 2 4n+8
- 2 CARD16 2 n
- 2 n 4n LISTofKEYSYM

#### BELLFEEDBACKSTATE

- 1 1 1 CARD8
- 1 CARDo
- 1 CARD8
- 3
- 2 CARD16
- 2 CARD16

#### LEDFEEDBACKSTATE

1	1	
1	CARD8	
2	10	

2	12
4	CARD32

- 4 CARD32 4 BITMASK #x0001
  - #x0001 On #x0002 Off

feedback class id id of this feedback length max\_symbols number of keysyms supported key symbols supported

feedback class id id of this feedback

minimum value

maximum value

length

resolution

- feedback class id id of this feedback length percent unused pitch duration
- feedback class id id of this feedback length led\_mask led\_values

1	CARD8	input extension opcode
1	23	ChangeFeedbackControl opcode
2	3+n/4	request length
4	BITMASK	value-mask (has n bits set to 1)
	#x0001	keyclick-percent
	#x0002	bell-percent
	#x0004	bell-pitch
	#x0008	bell-duration
	#x0010	led
	#x0020	led-mode
	#x0040	key
	#x0080	auto-repeat-mode
	#x0001	string
	#x0001	integer
	#x0001	acceleration-numerator
	#x0002	acceleration-denominator
	#x0004	acceleration-threshold
1	CARD8	device id
1	CARD8	feedback class id
2		unused
n	FEEDBACKCL	ASS

# FEEDBACKCLASS KBDFEEDBACKCTL, PTRFEEDBACKCTL, INTEGERFEEDBACKCTL, STRINGFEEDBACKCTL, BELLFEEDBACKCTL, or LEDFEEDBACKCTL

# KBDFEEDBACKCTL

RDF	EEDBACKCIL		
1	0		feedback class id
1	CARD8		id of this feedback
2	20		length
1	KEYCODE		key
1			auto-repeat-mode
	0	Off	
	1	On	
	2	Default	
1	INT8		key-click-percent
1	INT8		bell-percent
2	INT16		bell-pitch
2	INT16		bell-duration
4	CARD32		led_mask
4	CARD32		led_values

# PTRFEEDBACKCTL

1	1	feedback class id
1	CARD8	id of this feedback
2	12	length
2		unused
2	INT16	numerator
2	INT16	denominator
2	INT16	threshold

# STRINGCTL

1	2	feedback class id
1	CARD8	id of this feedback
2	4n+8	length
2		unused
2	n	number of keysyms to display
4n	LISTofKEYSYM	list of key symbols to display

1	ERCTL 3	feedback class id
1 2 4	CARD8 8 INT32	id of this feedback length integer to display
LEDC	ΓI.	
1	4	feedback class id
1 2	CARD8 12	id of this feedback length
4	CARD32	led_mask
4	BITMASK #x0001 On	led_values
	#x0002 Off	
BELLO	CTL 5	feedback class id
1	CARD8	id of this feedback
2	8	length
1 3	INT8	percent unused
2	INT16	pitch
2	INT16	duration
	ceKeyMapping	
1 1	CARD8 24	input extension opcode GetDeviceKeyMapping opcode
2	2	request length
1	CARD8	device
1 1	KEYCODE CARD8	fi rst-keycode count
1		unused
=>		
1	1 24	Reply GetDeviceKeyMapping opcode
2	CARD16	sequence number
4	nm	reply length (m = count fi eld from the request)
1 23	n	keysyms-per-keycode unused
4nm	LISTofKEYSYM	keysyms
	DeviceKeyMapping	· · · · ·
1	CARD8 25	input extension opcode ChangeDeviceKeyMapping opcode
2	2+nm	request length
1	CARD8	device
1 1	KEYCODE m	fi rst-keycode keysyms-per-keycode
1	n	keycode-count
4nm	LISTofKEYSYM	keysyms
	ceModifi erMapping	
1 1	CARD8 26	input extension opcode GetDeviceModifi erMapping opcode
2	2	request length
1	CARD8	device
3		unused

=> 1 1 2 4 1 23 8n	l 26 CARD16 2n n LISTofKEYCODE	3	Reply GetDeviceModifi erMapping opcode sequence number reply length keycodes-per-modifi er unused keycodes
SetDevi 1 2 1 1 2 8n	ceModifi erMapping CARD8 27 2+2n CARD8 n LISTofKEYCODE		input extension opcode SetDeviceModifi er opcode request length device keycodes-per-modifi er unused keycodes
=> 1 1 2 4 1 23	1 27 CARD16 0 1 2	Success Busy Failed	Reply SetDeviceModifi erMapping opcode sequence number reply length status unused
GetDevi 1 2 1 3	iceButtonMapping CARD8 28 2 CARD8		input extension opcode GetDeviceButtonMapping opcode request length device unused
=> 1 1 2 4 1 23 n p	l 28 CARD16 (n+p)/4 n LISTofCARD8		Reply GetDeviceButtonMapping opcode sequence number reply length number of elements in map list unused map unused, p=pad(n)
SetDevi 1 2 1 1 2 n p	ceButtonMapping CARD8 29 2+(n+p)/4 CARD8 n LISTofCARD8		input extension opcode SetDeviceButtonMapping opcode request length device length of map unused map unused, p=pad(n)

=> 1 1 2 4 1 23	1 29 CARD16 0 1	Success Busy	Reply SetDeviceButtonMapping opcode sequence number reply length status unused
QueryDe	eviceState		
1 1 2 1 3	CARD8 30 2 CARD8		input extension opcode QueryDeviceState opcode request length device unused
=>			
1 1 2 4 1 23 m	1 30 CARD16 m/4 n LISTofINPUTSTA	TE	Reply QueryDeviceState opcode sequence number reply length number of input classes unused
111		IL.	
	~		
INPUT	STATE	KEYSTATE or BU	<b>JTTONSTATE or VALUATORSTATE</b>
KEYST 1	TATE CARD8	KEYSTATE or BU	key input class id
KEYST 1 1 1	TATE	KEYSTATE or BU	key input class id length num_keys
KEYST 1 1	TATE CARD8 36	KEYSTATE or BU	key input class id length
KEYST 1 1 1 1 32	TATE CARD8 36 CARD8 LISTofCARD8	KEYSTATE or BU	key input class id length num_keys unused
KEYST 1 1 1 32 BUTTC 1	TATE CARD8 36 CARD8	KEYSTATE or BU	key input class id length num_keys unused status of keys button input class id
KEYST 1 1 1 32 BUTTC 1 1	TATE CARD8 36 CARD8 LISTofCARD8 DNSTATE CARD8 36	KEYSTATE or BU	key input class id length num_keys unused status of keys button input class id length
KEYST 1 1 1 32 BUTTC 1 1 1	TATE CARD8 36 CARD8 LISTofCARD8 DNSTATE CARD8	KEYSTATE or BU	key input class id length num_keys unused status of keys button input class id length num_buttons
KEYST 1 1 1 32 BUTTC 1 1	TATE CARD8 36 CARD8 LISTofCARD8 DNSTATE CARD8 36	KEYSTATE or BU	key input class id length num_keys unused status of keys button input class id length
KEYST 1 1 1 32 BUTTC 1 1 1 1 32	CATE CARD8 36 CARD8 LISTofCARD8 DNSTATE CARD8 36 CARD8 LISTofCARD8	KEYSTATE or BU	key input class id length num_keys unused status of keys button input class id length num_buttons unused
KEYST 1 1 1 32 BUTTC 1 1 1 1 32	TATE CARD8 36 CARD8 LISTofCARD8 DNSTATE CARD8 36 CARD8	KEYSTATE or BU	key input class id length num_keys unused status of keys button input class id length num_buttons unused status of buttons
KEYST 1 1 1 32 BUTTO 1 1 1 32 VALUA	TATE CARD8 36 CARD8 LISTofCARD8 DNSTATE CARD8 36 CARD8 LISTofCARD8	KEYSTATE or BU	key input class id length num_keys unused status of keys button input class id length num_buttons unused status of buttons valuator input class id length
KEYST 1 1 1 32 BUTTO 1 1 1 32 VALUA 1 1 1 1	TATE CARD8 36 CARD8 LISTofCARD8 DNSTATE CARD8 36 CARD8 LISTofCARD8 ATORSTATE CARD8	KEYSTATE or BU	key input class id length num_keys unused status of keys button input class id length num_buttons unused status of buttons valuator input class id length number of valuators
KEYST 1 1 1 32 BUTTO 1 1 1 32 VALUA 1 1	CATE CARD8 36 CARD8 LISTofCARD8 DNSTATE CARD8 36 CARD8 LISTofCARD8 ATORSTATE CARD8 4n + 4 n		key input class id length num_keys unused status of keys button input class id length num_buttons unused status of buttons valuator input class id length number of valuators mode
KEYST 1 1 1 32 BUTTO 1 1 1 32 VALUA 1 1 1 1	CATE CARD8 36 CARD8 LISTofCARD8 DNSTATE CARD8 36 CARD8 LISTofCARD8 ATORSTATE CARD8 4n + 4 n	DeviceMode (0 = 1	key input class id length num_keys unused status of keys button input class id length num_buttons unused status of buttons valuator input class id length number of valuators mode Relative, 1 = Absolute)
KEYST 1 1 1 32 BUTTO 1 1 1 32 VALUA 1 1 1 1	CATE CARD8 36 CARD8 LISTofCARD8 DNSTATE CARD8 36 CARD8 LISTofCARD8 ATORSTATE CARD8 4n + 4 n	DeviceMode (0 = 1	key input class id length num_keys unused status of keys button input class id length num_buttons unused status of buttons valuator input class id length number of valuators mode

1 1 2 4 1 1 2 1 3 32n	ensionEvent CARD8 31 4 + 8n + m WINDOW CARD8 BOOL CARD16 CARD8 LISTofEVENTS LISTofEVENTCL	ASS	input extension op SendExtensionEve request length destination device propagate eventclass count num_events unused events to send desired events	
	CARD8 32 2 CARD8 CARD8 CARD8 CARD8 INT8		input extension op DeviceBell opcode request length device id feedback id feedback class percent	
SetDevie 1 2 1 1 1 1 4n	ceValuators CARD8 33 2 + n CARD8 CARD8 n LISTofINT32	valuator values to	input extension op SetDeviceValuator request length device id fi rst valuator number of valuator unused set	s opcode
=> 1 1 2 4 1 23	1 33 CARD16 0 CARD8 0 1	Success AlreadyGrabbed		Reply SetDeviceValuators opcode sequence number reply length status unused
GetDevi 1 2 2 1 1	ceControl CARD8 34 2 CARD16 CARD8		input extension op GetDeviceControl request length device control type device id unused	opcode
=> 1 2 4 1 23 n	1 34 CARD16 n/4 CARD8 0 1 3 + fi rst_error			Reply GetDeviceControl opcode sequence number reply length status Success AlreadyGrabbed DeviceBusy unused DEVICESTATE

#### DEVICESTATE

#### DEVICERESOLUTIONSTATE

#### DEVICERESOLUTIONSTATE

2	0	control type
2	8 + 12n	length
4	n	num_valuators
4n	LISTOfCARD32	resolution values
4n	LISTOfCARD32	resolution min_values
4n	LISTOfCARD32	resolution max_values

# ChangeDeviceControl

1	CARD8	input extension opcode
1	35	ChangeDeviceControl opcode
2	2+n/4	request length
2	CARD16	control type
1	CARD8	device id
1		unused
n		DEVICECONTROL

#### DEVICECONTROL

DEVICERESOLUTIONCTL

#### DEVICERESOLUTIONCTL

2	1		control type
2	8 + 4n		length
1	CARD8		fi rst_valuator
1	n		num_valuators
2			unused
4n	LISTOfCARD32	resolution values	

# =>

1	1	Reply
1	35	ChangeDeviceControl opcode
2	CARD16	sequence number
4	0	reply length
1	CARD8	status
	0	Success
	1	AlreadyGrabbed
	3 + fi rst_error	DeviceBusy
23		unused

# Events

DeviceKeyPress, DeviceKeyRelease, DeviceButtonPress, DeviceButtonRelease, ProximityIn, ProximityOut, and DeviceStateNotify events may be followed by zero or more DeviceValuator events. DeviceMotionNotify events will be followed by one or more DeviceValuator events.

DeviceValuator

1	CARD8	code
1	CARD8	device id
2	CARD16	sequence number
2	SETofKEYBUTMASK	state
1	n	number of valuators this device reports
1	m	number of first valuator in this event
24	LISTofINT32 valuators	

Device	KeyPress	
1	CARD8	code
1	KEYCODE	detail
2	CARD16	sequence number
4	TIMESTAMP	time
4	WINDOW	root
4	WINDOW	event
4	WINDOW	child
	0 None	2
2	INT16	root-x
2	INT16	root-y
2	INT16	event-x
2	INT16	event-y
2	SETofKEYBUTMASK	state
1	BOOL	same-screen
1	CARD8	device id
	#x80	MORE_EVENTS follow
Device	KeyRelease	
1	CARD8	code
1	KEYCODE	detail
2	CARD16	sequence number
4	TIMECTAMD	times

2	CARDIO	sequence number
4	TIMESTAMP	time
4	WINDOW	root
4	WINDOW	event
4	WINDOW	child
	0 None	
2	INT16	root-x
2	INT16	root-y
2	INT16	event-x
2	INT16	event-y
2	SETofKEYBUTMASK	state
1	BOOL	same-screen
1	CARD8	device id
	#x80	MORE_EVENTS follow

# DeviceButtonPress

1	CARD8	code
1	BUTTON	detail
2	CARD16	sequence number
4	TIMESTAMP	time
4	WINDOW	root
4	WINDOW	event
4	WINDOW	child
	0 None	
2	INT16	root-x
2	INT16	root-y
2	INT16	event-x
2	INT16	event-y
2	SETofKEYBUTMASK	state
1	BOOL	same-screen
1	CARD8	device id
	#x80	MORE_EVENTS follow

DeviceB	uttonRelease		
1	CARD8		code
1	BUTTON		detail
2	CARD16		sequence number
4	TIMESTAMP		time
4	WINDOW		root
4	WINDOW		event
4	WINDOW		child
	0	None	
2	INT16		root-x
2	INT16		root-y
2	INT16		event-x
2	INT16		event-y
2	SETofKEYBUTM	ASK	state
1	BOOL		same-screen
1	CARD8		device id
	#x80		MORE_EVENTS follow
DeviceM	IotionNotify		
1	CARD8		code
1			detail
	0	Normal	

	0	Normal	
	1	Hint	
2	CARD16		sequence number
4	TIMESTAMP		time
4	WINDOW		root
4	WINDOW		event
4	WINDOW		child
	0	None	
2	INT16		root-x
2	INT16		root-y
2	INT16		event-x
2	INT16		event-y
2	SETofKEYBUTM	ASK	state
1	BOOL		same-screen
1	CARD8		device id
	#x80		MORE_EVENTS follow

#### DeviceFocusIn

1	CARD8		code
1			detail
	0	Ancestor	
	1	Virtual	
	2	Inferior	
	3	Nonlinear	
	4	NonlinearVirtual	
	5	Pointer	
	6	PointerRoot	
	7	None	
2	CARD16		sequence number
4	TIMESTAMP		time
4	WINDOW		event
1			mode
	0	Normal	
	1	Grab	
	2	Ungrab	
	3	WhileGrabbed	
1	CARD8		device id
18			unused

#x80

DeviceF			
1	CARD8		code
1			detail
	0	Ancestor	
	1	Virtual	
	2	Inferior	
	3	Nonlinear	
	4	NonlinearVirtual	
	5	Pointer	
	6	PointerRoot	
	7	None	
2	, CARD16	None	sequence number
4	TIMESTAMP		sequence number time
4	WINDOW		event
1	0		mode
	0	Normal	
	1	Grab	
	2	Ungrab	
	3	WhileGrabbed	
1	CARD8		device id
18			unused
	_		
Proximit			
1	CARD8		code
1			unused
2	CARD16		sequence number
4	TIMESTAMP		time
4	WINDOW		root
4	WINDOW		event
4	WINDOW		child
•	0	None	china
2	INT16	None	root-x
2			
	INT16		root-y
2	INT16		event-x
2	INT16		event-y
2	SETofKEYBUTM	ASK	state
1	BOOL		same-screen
1	CARD8		device id
	#x80		MORE_EVENTS follow
D			
Proximit			
1	CARD8		code
1	C D D L C		unused
2	CARD16		sequence number
4	TIMESTAMP		time
4	WINDOW		root
4	WINDOW		event
4	WINDOW		child
	0	None	
2	INT16		root-x
2	INT16		root-y
2	INT16		event-x
$\frac{2}{2}$	INT16		event-y
2	SETofKEYBUTM	A SK	•
		лы	state
1	BOOL		same-screen
1	CARD8		device id

DeviceStateNotify events may be immediately followed by zero or one DeviceKeyStateNotify and/ or zero or more DeviceValuator events.

MORE\_EVENTS follow

DeviceSi 1 1	tateNotify CARD8 CARD8		code device id
	#x80		MORE_EVENTS follow
2	CARD16		sequence number
4	TIMESTAMP		time
1	CARD8		num_keys
1	CARD8		num_buttons
1	CARD8 CARD8		num_valuators
1	#x01	reporting keys	valuator mode and input classes reported
	#x02	reporting buttons	
	#x04	reporting valuators	
	#x40	device mode $(0 = R)$	Relative, 1 = Absolute)
	#x80		= InProximity, 1 = OutOfProximity)
4	LISTofCARD8		fi rst 32 keys (if reported)
4	LISTofCARD8		fi rst 32 buttons (if reported)
12	LISTofCARD32		fi rst 3 valuators (if reported)
DeviceK	eyStateNotify		
1	CARD8		code
1	CARD8		device id
2	#x80 CARD16		MORE_EVENTS follow sequence number
$\frac{2}{28}$	LISTofCARD8		state of keys 33-255
20	LIGIOLOM		state of Keys 55-255
р <sup>,</sup> р			
DeviceB 1	uttonStateNotify CARD8		code
1	CARD8		device id
1	#x80		MORE_EVENTS follow
2	CARD16		sequence number
28	LISTofCARD8		state of buttons 33-255
DeviceV	aluator		
1	CARD8		code
1	CARD8		device id
2	CARD16		sequence number
2	SETofKEYBUTM	ASK	state
1 1	n n		number of valuators this device reports number of first valuator in this event
24	LISTofINT32	valuators	number of it ist valuator in this event
21	LIGIOIII(192	valuators	
DaviaaN	[anningNatify		
1	lappingNotify CARD8		code
1	CARD8		device id
2	CARD16		sequence number
1			request
	0	MappingModifier	
	1	MappingKeyboard	
1	2 KEVCODE	MappingPointer	f and have a de
1 1	KEYCODE CARD8		fi rst-keycode count
1	CARDO		unused
4	TIMESTAMP		time
20			unused

Changel	DeviceNotify		
1	CARD8		code
1	CARD8		id of device specifi ed on change request
2	CARD16		sequence number
4	TIMESTAMP		time
1			request
	0	NewPointer	
	1	NewKeyboard	
23			unused

# **Table of Contents**

1.1. Input Extension Overview	1
1.2. Design Approach	1
1.3. Core Input Devices	1
1.4. Extension Input Devices	1
1.4.1. Event Classes	2
1.4.2. Input Classes	2
2. Requests	3
2.1. Getting the Extension Version	3
2.2. Listing Available Devices	3
2.3. Enabling Devices	5
2.4. Changing The Mode Of A Device	7
2.5. Initializing Valuators on an Input Device	7
2.6. Getting Input Device Controls	7
2.7. Selecting Extension Device Events	9
2.8. Determining Selected Events	10
2.9. Controlling Event Propagation	10
2.10. Sending Extension Events	11
2.11. Getting Motion History	11
2.12. Changing The Core Devices	12
2.13. Event Synchronization And Core Grabs	14
2.14. Extension Active Grabs	14
2.15. Passively Grabbing A Key	15
2.16. Passively Grabbing A Button	17
2.17. Thawing A Device	18
2.18. Controlling Device Focus	19
2.19. Controlling Device Feedback	20
2.20. Ringing a Bell on an Input Device	24
2.21. Controlling Device Encoding	25
2.22. Controlling Button Mapping	27
2.23. Obtaining The State Of A Device	28
3. Events	29
3.1. Button, Key, and Motion Events	29
3.2. Device Valuator Event	30
3.3. Device Focus Events	30
3.4. Device State Notify Event	30
3.5. Device KeyState and ButtonState Notify Events	31
3.6. DeviceMappingNotify Event	31
3.7. ChangeDeviceNotify Event	32
3.8. Proximity Events	32
Appendix A – Input Extension Protocol Encoding	33